


```

LL          IIIII
LL          IIIII
LL          II
LL          II
LL          II
LL          II
LL          II
LL          II
LL          II
LL          II
LL          II
LL          II
LL          II
LLL        IIIII
LLL        IIIII
SSSSSSSSS
SSSSSSSSS
SS
SS
SS
SS
SSSSSS
SSSSSS
SS
SS
SS
SS
SSSSSSSSS
SSSSSSSSS

```

(1)	2	copyright notice
(1)	29	Program description
(2)	100	declarations
(3)	152	storage definitions
(4)	201	read-only data definitions
(5)	345	display_devbyaddr -- display UCB, etc. given its address
(6)	413	display_device -- display i/o data structures
(7)	511	parse_device -- parse device name into name and unit number
(8)	569	show_ddbs -- display device data blocks (DDBs)
(9)	658	get_ddb -- locate the next DDB in the I/O database
(10)	755	show_controller, Display controller information
(10)	873	show_controller tables & action routines
(11)	1188	show_system_block, show system/path blocks (SB/PB)
(11)	1254	show_system_block tables & action routines
(12)	1504	show_ucb, show unit control block (UCB)
(12)	1670	get_ucb, copy UCB to local storage
(12)	1700	show_ucb tables & action routines
(13)	2054	show_ioq, Display I/O queue for device
(14)	2145	show_acpq, display acp queue
(14)	2230	volume control block tables & action routines
(15)	2301	print_cdrp, print a single CDRP block
(16)	2389	print_irp, print a single IRP block
(17)	2471	show_vcb, Display Volume Control Block (VCB)
(17)	2609	volume control block tables & action routines
(18)	2742	show_cddb, Display Class Driver Data Block (CDDB)
(19)	2808	class driver data block tables & action routines

DEVICE
V04-000

Display device data structures

G 11

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 1
(1)

DE
VC

```
0000 1      .title device Display device data structures
0000 2      .sbttl copyright notice
0000 3      .ident 'V04-000'
0000 4      :
0000 5      :*****
0000 6      :
0000 7      :*  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8      :*  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9      :*  ALL RIGHTS RESERVED.
0000 10     :*
0000 11     :*  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12     :*  ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13     :*  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14     :*  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15     :*  OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16     :*  TRANSFERRED.
0000 17     :*
0000 18     :*  THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19     :*  AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20     :*  CORPORATION.
0000 21     :*
0000 22     :*  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23     :*  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24     :*
0000 25     :*
0000 26     :*****
0000 27     :
```

```

0000 29      .sbtll Program description
0000 30      :++
0000 31      Facility
0000 32      :
0000 33      System Dump Analyzer
0000 34      :
0000 35      Abstract
0000 36      :
0000 37      This module contains routines to print device data
0000 38      structures for the i/o subsystem.
0000 39      :
0000 40      Environment
0000 41      :
0000 42      Native mode, User mode
0000 43      :
0000 44      Author
0000 45      :
0000 46      Tim Halvorsen, July 1978
0000 47      :
0000 48      Modified by
0000 49      :
0000 50      V03-011 EMB0110      Ellen M. Batbouta      24-Jul-1984
0000 51      Fix a typo in the SHOW DEVICE display and update the
0000 52      list of devices and device characteristics.
0000 53      :
0000 54      V03-010 EMB0105      Ellen M. Batbouta      07-Jun-1984
0000 55      Add routines to display the contents of the class
0000 56      driver data blocks (CDDb) when displaying an mscp
0000 57      served device. Also for mscp served devices check
0000 58      2 additional queues before drawing the conclusion
0000 59      that the io request queue is empty. Fix a minor
0000 60      bug and include the node name in the display in
0000 61      the routine, SHOW_SYSTEM_BLOCK.
0000 62      :
0000 63      V03-009 EMD0082      Ellen M. Dusseault      12-Apr-1984
0000 64      Print the address of the cddb and the alternate cddb
0000 65      (if the device is mscp served) when displaying the ucb tables
0000 66      and action routines. Also display the reasons to wait
0000 67      count for mscp served devices.
0000 68      :
0000 69      V03-008 LMP0221      L. Mark Pilant,          30-Mar-1984 11:53
0000 70      Change UCBSL_OWNUIC to ORBSL_OWNER and UCBSW_VPROT to
0000 71      ORBSW_PROT.
0000 72      :
0000 73      V03-007 EMD0059      Ellen M. Dusseault      07-Mar-1984
0000 74      Fill in local ucb with zeroes in routine, GET_UCB,
0000 75      just in case next ucb fetched is shorter than the
0000 76      previous one.
0000 77      :
0000 78      V03-006 WHM0002      Bill Matthews            16 Feb-1984
0000 79      Change IDBSB_COMBO_VECTOR back to IDBSB_VECTOR.
0000 80      :
0000 81      V03-005 TMK0002      Todd M. Katz              29-Jan-1984
0000 82      Add DTS_NI to the table BUS_TYPE.
0000 83      :
0000 84      V03-004 WHM0001      Bill Matthews            16-Jan-1984
0000 85      Change IDBSB_VECTOR to IDBSB_COMBO_VECTOR.

```

0000	86	:			
0000	87	:			
0000	88	:	V03-003	TMK0001	Todd M. Katz
0000	89	:			19-Nov-1983
0000	90	:			Change DT\$ UNA11 to DT\$ DEUNA in the table SCOM_TYPE and
0000	91	:			add DT\$ DECUA to the same table.
0000	92	:	V03-002	ROW0237	Ralph O. Weber
0000	93	:			10-OCT-1983
0000	94	:			Enhance all displays for latest and greatest I/O database
0000	95	:			information. Add support for SHOW DEVICE/ADDR <expr>, where
0000	96	:			expression is a UCB address.
0000	97	:	V03-001	KTA3041	Kerbey T. Altmann
0000	98	:			26-Apr-1983
					Fix for cluster names.

```
0000 100      .sbttl  declarations
0000 101      :
0000 102      :
0000 103      :
0000 104      $adpdef      : Adapter Control Block (ADP)
0000 105      $aqbdef      : ACP queue header block (aqb)
0000 106      $cddbdef     : Class Driver Data Block (Cddb)
0000 107      $cdrpdef     : Class Driver Request Packet (CDRP)
0000 108      $crbdef      : channel request block (CRB)
0000 109      $dcdef       : device class/type definitions
0000 110      $ddbdef      : device data block (ddb)
0000 111      $ddtdef      : Driver dispatch table (DDT)
0000 112      $devdef      : Device characteristics definitions
0000 113      $dptdef      : Driver prologue table (DPT)
0000 114      $dyndef      : Dynamic storage type definitions
0000 115      $idbdef      : interrupt dispatch block (IDB)
0000 116      $iodef       : I/O function codes
0000 117      $irpdef      : I/O request package (IRP)
0000 118      $mscpdef     : Mass Storage Control Protocol (MSCP)
0000 119      $orbdef      : Object's Rights Block (ORB)
0000 120      $pbdef       : path block (PB)
0000 121      $pcbdef      : Process control block (PCB)
0000 122      $sbdef       : System block (SB)
0000 123      $tpadef      : TPARSE definitions
0000 124      $ttyucbdef    : terminal UCB definitions
0000 125      $ucbdef      : unit control block (UCB)
0000 126      $vcbdef      : Volume control block (VCB)
0000 127      $vecdef      : interrupt transfer vector (in IDB)
0000 128      :
0000 129      :
0000 130      : definition of requested device name storage fields
0000 131      : (using storage based at parsed_devnam)
0000 132      :
0000 133      $defini pdvnm
0000 134 $def  pdvnm_t_node  .blkb 16      : node name
0010 135 $def  pdvnm_t_ddc  .blkb 16      : device & controller
0020 136 $def  pdvnm_w_unit  .blkw 1       : unit number
0022 137 $def  pdvnm_b_nodesz .blkb 1     : size of real node name
0023 138      : (use by get_ddb)
00000024 0023 139      .blkb 1
00000024 0024 140 pdvnm_k_length = .          : size of this structure
0024 141      $defend pdvnm
0000 142      :
0000 143      :
0000 144      : definition of flags bits stored in r8 by display_device
0000 145      :
0000 146      _vield  flag,0,< -
0000 147      <one_unit,,m>, - : a specific unit was specified
0000 148      <alt_path,,m>, - : traversing the alternate DDB chain
0000 149      <fnd_unit,,m>, - : found at least one unit
0000 150      >
```

```
0000 152 .sbttl storage definitions
0000 153 :
0000 154 : storage definitions
0000 155 :
0000 156 :
00000000 157 .psect sdadata,noexe,wrt
0000 158
000000CC 0000 159 ucb_size = ucb$k_lcl_disk_length
0000 160 .iif gt <ucb$l_2p_cddb+4-ucb_size>, ucb_size = ucb$l_2p_cddb+4
0000 161
00000060 0000 162 sb: .blkb sb$k_length ; System block (SB)
0000 163 nodnam_2p:
00000071 0060 164 .blkb sb$s_nodename+1
0000 165
000000B5 0071 166 ddb: .blkb ddb$k_length ; device data block (DDB)
000000F9 00B5 167 ddb_2p: .blkb ddb$k_length ; secondary device data block (DDB)
0000 168
000001C5 00F9 169 ucb: .blkb ucb_size ; unit control block (UCB)
0000 170 ; all the interesting stuff
0000 171
00000289 01C5 172 irp: .blkb irp$c_length ; I/O request package (IRP)
0000 173
00000331 0289 174 cdrp: .blkb cdrp$c_cd_len-cdrp$l_ioqfl ; Class Driver Request Package (CDRP)
000000A8 0331 175 cdrp_length=cdrp$c_cd_len-cdrp$l_ioqfl ; Total length of cdrp including negative of
0000 176
0000041D 0331 177 vcb: .blkb vcb$c_length ; Volume control block (VCB)
0000 178
00000439 041D 179 aqb: .blkb aqb$c_length ; ACP queue header block (aqb)
0000 180
00000471 0439 181 dpt: .blkb dpt$c_length ; Driver prologue table (DPT)
0000 182
000004E1 0471 183 cddb: .blkb cddb$k_length ; Class driver data block (CDDb)
0000 184
00000551 04E1 185 cddb_2p: .blkb cddb$k_length ; Secondary CDDb
0000 186
0000 187 parsed_devnam:
00000575 0551 188 .blkb pdvnm_k_length
0000 189
0000 190 flag_2nd_cddb:
0000 191 .word 0 ; flag to tell us if the address coming in is the
0000 192 ; primary or secondary cddb in routine, show_cddb
0000 193 queue_notempty:
00 0577 194 .byte 0 ; if 1 means item in an io queue to be displayed
0000 195 ; if 0 the queue is empty
0000 196
00000000 197 .psect device,exe,nowrt,long
0000 198
0000 199 .default displacement,long
```



```

0000 201      .sbttl  read-only data definitions
0000 202
0000 203  :
0000 204      read-only data definitions
0000 205  :
0000 206
0000 207 pb_status:
0000 208      table  pb$V_,<tim>
0010 209
0010 210 pb_state:
0010 211      table  pb$c_,<CLOSED,ST_SENT,ST_REC,OPEN>
0038 212
0038 213 pb_rstate:
0038 214      table  pb$c_,<UNINIT,DISAB,ENAB>
0058 215
0058 216 pb_rport_type:
0058 217      table  pb$c_,<CI780,HSC,KL10,CINT,NI,PS>
0090 218
0090 219 ddb_acpclass:
0090 220      table  ddb$k_,<PACK,CART,SLOW,TAPE>
0088 221
0088 222 unit_status:
0088 223      table  ucb$V_,<tim,int,erlogip,cancel,online,power,timeout,-
0088 224      inttype,bsy,mounting,deadmo,valid,unload,template,-
0088 225      mntverip,wrongvol,deleteucb,lcl_valid,supmvmmsg,-
0088 226      mntverpnd>
0160 227
0160 228 device_char:
0160 229      table  dev$V_,<rec,ccl,trm,dir,sdi,sqd,spl,opr,rct,net,fod,-
0160 230      dua,shr,gen,avl,mnt,mbx,dmt,elg,all,for,swl,idv,odv,-
0160 231      rnd,rtm,rck,wck>
0248 232
0248 233 device_char_2:
0248 234      table  dev$V_,<clu,det,rtt,cdp,2p,mscp,ssm,svr,red,nnm>
02A0 235
02A0 236 device_class:
02A0 237      addr_table dc$ <-
02A0 238      <disk,disk_type>,-
02A0 239      <tape,tape_type>,-
02A0 240      <scom,scom_type>,-
02A0 241      <card,card_type>,-
02A0 242      <term,term_type>,-
02A0 243      <lp,lp_type>,-
02A0 244      <workstation,workstation_type>,-
02A0 245      <realtime,realtime_type>,-
02A0 246      <bus,bus_type>,-
02A0 247      <mailbox,mailbox_type>,-
02A0 248      <journal,journal_type>,-
02A0 249      <misc,misc_type>-
02A0 250      >
0308 251
0308 252 disk_type:
0308 253      table  dt$,<RK06,RK07,RP04,RP05,RP06,RM03,RP07,RP07HT,RL01,RL02,-
0308 254      RX02,RX04,RM80,TU58,RM05,RX01,ML11,RB02,RB80,RA80,RA81,RA60,-
0308 255      RZ01,RC25,RZF01,RCF25,RD51,RX50,RD52,RD53,RD26,RA82,RC26,-
0308 256      RCF26,CRX50>
0428 257

```

```

0428 258 tape_type:
0428 259     table dt$, <TE16, TU45, TU77, TS11, TU78, TA78, TU80, TU81, TA81, TK50>
0480 260
0480 261 scom_type:
0480 262     table dt$, <DMC11, DMR11, XK 3271, XJ 2780, NW X25, NV X29, SB ISB11, -
0480 263     MX_MUX200, DMP11, DMF32, XV 327T, CI, NI, DEUNA, YR X25, YD X25, -
0480 264     YP_ADCCP, YQ_3271, YR_DDCMP, YS_SDLCL, UK_KTC32, DEQNA, DMV11, DELUA>
0548 265
0548 266 card_type:
0548 267     table dt$, <CR11>
0558 268
0558 269 term_type:
0558 270     table dt$, <TTYUNKN, VT05, FT1, FT2, FT3, FT4, FT5, FT6, FT7, FT8, LAX, -
0558 271     LA36, LA120, VT5X, VT52, VT55, IQ B1S, TEK401X, VT100, VK100, -
0558 272     VT173, LA34, LA38, LA12, LA24, LQP02, VT101, VT102, VT105, VT125, -
0558 273     VT131, VT132, DZ11, DZ32, DZ730, DMZ32, DHV, DHU>
0690 274
0690 275 lp_type:
0690 276     table dt$, <LP11, LA11, LA180>
0680 277
0680 278 workstation_type:
0680 279     table dt$, <VS100, VS125, VS300>
0600 280
0600 281 realtime_type:
0600 282     table dt$, <LPA11, DR780, DR750, DR11W, PCL11R, PCL11T, DR11C, XI_DR11C, -
0600 283     XP_PCL11B, IX_IEX11>
0728 284
0728 285 bus_type:
0728 286     table dt$, <CI780, CI750, UQPORT, UDA50, UDA50A, LESI, TU81P, RDRX, NI>
0778 287
0778 288 mailbox_type:
0778 289     table dt$, <MBX, SHRMBX, NULL>
0798 290
0798 291 journal_type:
0798 292     table dt$, <RUJNL, BIJNL, AIJNL, ATJNL, CLJNL>
0708 293
0708 294 misc_type:
0708 295     table dt$, <DN11>
0708 296
0708 297 vcb_disk_status:
0708 298     table vcb$v, <write_if, write_sm, homblkb, idxhdrbad, noalloc, -
0708 299     extfid, group, system>
0820 300
0820 301 vcb_disk_status2:
0820 302     table vcb$v, <writethru, nocache, mountver, erase, nohighwater>
0850 303
0850 304 vcb_tape_status:
0850 305     table vcb$v, <partfile, logiceovs, waimouvol, wairewind, waiusrlbl, -
0850 306     cancelio, mustclose, nowrite>
0898 307
0898 308 vcb_tape_mode:
0898 309     table vcb$v, <ovrexp, ovracc, ovrlbl, ovrsetid, intchg, ebclic, novol2, -
0898 310     starfile, enusereot, blank, init, noauto, ovrvol>
0908 311
0908 312 vcb_journal_char:
0908 313     table vcb$v, <jnl_disk, jnl_tape, jnl_tmpfi>
0928 314

```

```

0928 315 cddb_status:
0928 316         table  cddb$V_,<snlstrm,impend,initing,reconnect,resynch,polling,-
0928 317                                alcls_set,noconn,rstrtwait,quorlost,dapbsy,2pbsy>
0990 318
0990 319 cddb_flags:
0990 320         table  mscp$V_,<cf_576,cf_shadw,cf_mlths,cf_this,cf_other,cf_misc,-
0990 321                                cf_attn,cf_replc>
09D8 322
09D8 323 cdrp_dutuflags:
09D8 324         table  cdrp$V_,<cand,canio,erlip,perm,hirt,ivcmd>
0A10 325
0A10 326 request_status:
0A10 327         table  irp$V_,<bufio,func,pagio,complx,virtual,chained,swapio,-
0A10 328                                diagbuf,physio,termio,mbxio,extend,filacp,mvirp>
0A88 329
0A88 330 io_function:
0A88 331         table  io$_,<nop,unload,seek,recal,erasetape,packack,spacercord,-
0A88 332                                writecheck,writpblk,readpblk,available,dse,setchar,sensechar,-
0A88 333                                writemark,wrttmkr,writelblk,readlblk,rewindoff,setmode,rewind,-
0A88 334                                skipfile,skiprecord,sensemode,writeof,writvblk,readvblk,-
0A88 335                                access,create,deaccess,delete,modify,acpcontrol>
0B98 336
0B98 337 acp_status:
0B98 338         table  aqb$V_,<unique,defclass,defsys,creating>
0BC0 339
0BC0 340 aqb_acptype:
0BC0 341         table  aqb$K_,<undefined,f11v1,f11v2,mta,net,rem,jnl>
0C00 342
0C00 343

```

```
0C00 345 .sbttl display_devbyaddr -- display UCB, etc. given its address
0C00 346 :---
0C00 347 :
0C00 348 display_devbyaddr
0C00 349 :
0C00 350 This routine takes the address value in TPA$ NUMBER(AP),
0C00 351 attempt to use it as a UCB address, and do a SHOW DEVICE
0C00 352 for that UCB. This is the primary support routine for
0C00 353 the SHOW DEVICE/ADDR command.
0C00 354 :
0C00 355 Inputs:
0C00 356 :
0C00 357 AP = pointer to TPARSE block
0C00 358 :
0C00 359 Outputs:
0C00 360 :
0C00 361 The i/o data structures for that device are shown.
0C00 362 :
0C00 363 :---
0C00 364 :
0C00 365 .enable lsb
0C00 366 :
ODFC 0C00 367 .entry display_devbyaddr, -
0C02 368 ^m<r2,r3,r4,r5,r6,r7,r8,r8,r10,r11>
0C02 369 :
0C02 370 subhd <I/O data structures>
57 000000F9'EF 9E 0C0F 371 movab ucb, r7 ; get local UCB home
52 1C AC D0 0C16 372 movl tpa$l_number(ap), r2 ; get supposed UCB address
136C 30 0C1A 373 bsbw get_ucb ; pull UCB to local memory
06 50 E9 0C1D 374 blbc r0, 900$ ; if error, exit
0A A7 10 91 0C20 375 cmpb #dyn$sc_ucb, ucb$b_type(r7) ; is it really a UCB?
4E 13 0C24 376 beql 10$ ; branch if really a UCB
1C AC DD 0C26 377 900$: pushl tpa$l_number(ap) ; else, output a error
006D 31 0C29 378 type 1, <IXC is not the address of a UCB>
0C71 379 brw 999$ ; then exit
0C74 380 :
56 00000071'EF 9E 0C74 381 10$: movab ddb, r6 ; get local DDB home
96 50 E9 0C8D 382 trymem @ucb$l_ddb(r7), (r6), #ddb$sk_length ; copy the DDB
0A A6 06 91 0C90 383 910$: blbc r0, 900$ ; quit now, if error
90 12 0C94 384 911$: cmpb #dyn$sc_ddb, ddb$b_type(r6) ; is this a DDB?
5B 00000000'EF 9E 0C96 385 911$: bneq 900$ ; branch if not a DDB
DB 50 E9 0C9D 386 movab sb, r11 ; get local SB home
0A AB 0760 8F B1 0CAF 387 trymem @ddb$l_sb(r6), (r11), #sb$sk_length ; copy the SB
DA 12 0CB8 388 blbc r0, 910$ ; if error, exit
10 38 A7 0E E1 0CB2 389 cmpw #<dyn$sc_scs_sba8+dyn$sc_scs>, - ; is this really a SB?
50 44 AB 9A 0CB8 390 sb$b_type(r11)
45 AB40 24 90 0CB8 391 bneq 911$ ; branch if no really a SB
44 AB 96 0CBA 392 :
03 11 0CBF 393 bbc #dev$sv_fod, ucb$l_devchar(r7), - ; branch if this device not
44 AB 94 0CC3 394 27$: movzbl sb$t_nodename(r11), r0 ; file oriented?
OCC5 395 beql 30$ ; else, get node name size
OCCA 396 movb #^a/$/, - ; branch if no node name
OCCD 397 sb$t_nodename+1(r11)[r0] ; add '$' to node name
OCCF 398 incb sb$t_nodename(r11) ; increase size of node name
400 399 brb 30$
401 27$: clrb sb$t_nodename(r11) ; non-fod devices have no node
```

DEVICE
V04-000

Display device data structures C 12
display_devbyaddr -- display UCB, etc. g 16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 10
(5)

```

      00 DD OCD2 402
    44 AB 9F OCD2 403 30$: pushl #0 ; setup no flags flags longword
      52 DD OCD4 404 pushab sb$t_nodename(r11) ; setup node name
      56 DD OCD7 405 pushl r2 ; setup UCB VA
    1C7B 7E 56 7D OCD9 406 movq r6, -(sp) ; setup local DDB and UCB
      CF 05 FB OCD0 407 calls #5, w^show_ucb ; display this UCB
      04 OCE1 408
      OCE1 409 999$: ret
      OCE2 410
      OCE2 411 .disable lsb
```

DEV
V04

```

OCE2 413 .sbttl display_device -- display i/o data structures
OCE2 414 :---
OCE2 415 :
OCE2 416 display_device
OCE2 417 :
OCE2 418 This routine displays all i/o data structures related
OCE2 419 to a specified generic device name.
OCE2 420 :
OCE2 421 Inputs:
OCE2 422 :
OCE2 423 AP = pointer to TPARSE block
OCE2 424 :
OCE2 425 Outputs:
OCE2 426 :
OCE2 427 The i/o data structures for that device are shown.
OCE2 428 :
OCE2 429 :---
OCE2 430 .enabl lsb
OCE2 431 :
OCE2 432 display_device::
OCE2 433 .word ^m<r2,r3,r4,r5,r6,r7,r8,r9,r10,r11>
OCE4 434 :
58 D4 OCE4 435 clr1 r8 ; init internal flags
00B4 30 OCE6 436 bsbw parse_device ; parse the device into name and unit
OCE9 437 :
OCE9 438 subhd <I/O data structures>
OCF6 439 :
OCF6 440 assume flag_v_one_unit eq 0
ODFD'CF 05 58 E8 OCF6 441 blbs r8, 10$ ; if explicit unit, skip ddb info
6C FA OCF9 442 callg (ap), w^show_ddbs ; show DDB summary
OCE2 443 :
OCE2 444 ; init iodb scan
58 D4 OCFE 445 10$: clr1 r11 ; make get_ddb initialize
OD00 446 :
OD00 447 ; loop over all DDBs and both paths
0202 30 OD00 448 20$: bsbw get_ddb ; get the next DDB
3C 50 E9 OD03 449 blbc r0, 25$ ; leave when done
57 000000F9'EF 9E OD06 450 movab ucb, r7 ; address UCB in local storage
58 02 CA OD0D 451 bicl #flag_m_alt_path, r8 ; assume not alternate path, yet
52 04 A6 D0 OD10 452 movl ddb$l_ucb(r8), r2 ; Address of first UCB
06 13 OD14 453 beql 30$ ; Branch if none
1270 30 OD16 454 bsbw get_ucb ; Read first UCB
14 50 E8 OD19 455 blbs r0, 40$ ; If got something, go process it
52 40 A6 D0 OD1C 456 30$: movl ddb$l_dp_ucb(r6), r2 ; try looking at the alternate path
DE 13 OD20 457 beql 20$ ; branch if nothing there
1264 30 OD22 458 bsbw get_ucb ; read first alternate pathed UCB
F4 50 E9 OD25 459 blbc r0, 30$ ; if nothing there, skip this DDB
58 02 C8 OD28 460 bisl #flag_m_alt_path, r8 ; now doing the alternate path
04 A6 D5 OD2B 461 tstl ddb$l_ucb(r8) ; was anything found on primary path?
30 12 OD2E 462 bneq 60$ ; if so, skip the controller info
OD30 463 :
OD30 464 ; display controller information if appropriate
OD30 465 :
2D 58 E8 OD30 466 40$: assume flag_v_one_unit eq 0
59 DD OD33 467 blbs r8, 60$ ; if explicit unit, skip controler info
44 AB 9F OD35 468 pushl r9 ; SVA of DDB
7E 56 7D OD38 469 pushab sb$t_nodename(r11) ; address of nodename
movq r6, -Tsp) ; address of DDB,UCB blocks

```

```
0FE1'CF 03 FB 0D3B 470      calls #3,w^show_controller ; Display controller info
          28 11 0D40 471      brb 70$ ; ...enter loop
          0D42 472
          0D42 473 ; Intermediate branch to final cleanup/error processing.
          0D42 474
          3A 11 0D42 475 45$: brb 100$
          0D44 476
          0D44 477 ; loop over all UCBs on a either DDB chain
09 58 01 E1 0D44 478 50$: bbc #flag_v_alt_path, r8, - ; branch if using primary chain
          0D48 479 53$
52 00A4 C7 D0 0D48 480      movl ucb$l_dp_link(r7), r2 ; else, addr. of next UCB on sec. chain
          B1 13 0D4D 481      beql 20$ ; branch if no more
          06 11 0D4F 482      brb 55$ ; else, continue processing
52 30 A7 D0 0D51 483 53$: movl ucb$l_link(r7), r2 ; address of next UCB in primary chain
          C5 13 0D55 484      beql 30$ ; branch if no more
          122F 30 0D57 485 55$: bsbw get_ucb ; Get local copy of the UCB
          BF 50 E9 0D5A 486      blbc r0, 30$ ; skip rest if chain broken
          0A 58 E9 0D5D 487      assume flag_v_one_unit eq 0
          0D5D 488      blbc r8, 70$ ; branch if displaying all units
          0D60 489
00000571'EF 54 A7 B1 0D60 490 60$: cmpw ucb$w_unit(r7), - ; check if request unit
          DA 12 0D68 491      parsed_devnam+pdvnm_w_unit
          0D6A 492      bneq 50$ ; skip if not
          58 DD 0D6A 494 70$: pushl r8 ; flags longword
          44 AB 9F 0D6C 495      pushab sb$t_nodename(r11) ; address of node name
          52 DD 0D6F 496      pushl r2 ; actual address of UCB
          7E 56 7D 0D71 497      movq r6, -(sp) ; address of DDB,UCB blocks
1C7B'CF 05 FB 0D74 498      calls #5,w^show_ucb ; display current UCB
          58 04 C8 0D79 499      bisl #flag_m_fnd_unit, r8 ; mark at least 1 UCB was displayed
          C6 11 0D7C 500      brb 50$ ; loop thru all UCB's
          0D7E 501
          58 02 E0 0D7E 502 100$: bbs #flag_v_fnd_unit, - ; branch if at least 1 ucb displayed
          13 0D81 503      r8, 110$
50 0000'8F 3C 0D82 504      movzwl #ss$_nosuchdev, r0 ; signal 'no such device'
          0D87 505      signal 0
          0D95 506 110$: status success ; exit to tparse w/success
          04 0D9C 507      ret
          0D9D 508
          0D9D 509      .dsabl lsb
```

```

OD9D 511 .sbtll parse_device -- parse device name into name and unit number
OD9D 512 ---
OD9D 513 parse the device name into name and unit number
OD9D 514
OD9D 515 Inputs:
OD9D 516
OD9D 517 r8 = longword of show command status flags
OD9D 518 tpa$ tokencnt(ap) = Descriptor of device name
OD9D 519 parsed_devnam = address of a work area into which parsed fragments
OD9D 520 of the device name are stored
OD9D 521
OD9D 522 Outputs:
OD9D 523
OD9D 524 if x equals parsed_devnam then:
OD9D 525 pdvnm_t_node(x) = ASCII string for parsed node name
OD9D 526 pdvnm_t_ddc(x) = ASCII string for parsed device and controller
OD9D 527 pdvnm_s_unit(x) = converted unit number
OD9D 528 (null strings imply item missing from input)
OD9D 529 flag_m_one_unit in r8, set if unit number specified
OD9D 530 r2-r7 and r9-r11 are destroyed.
OD9D 531 ---
OD9D 532
OD9D 533 parse_device:
5B 00000551'EF 9E OD9D 534 movab parsed_devnam, r11 ; get working area base address
10 6B D4 ODA4 535 clrl pdvnm_t_node(r11) ; null the two string values
20 AB D4 ODA6 536 clrl pdvnm_t_ddc(r11)
56 10 AB B4 ODA9 537 clrw pdvnm_w_unit(r11) ; zero unit number
67 56 24 3A ODB0 538 movq tpa$ tokencnt(ap), r6 ; get descriptor of input string
59 51 14 13 ODB4 539 locc #a/$7, r6, (r7) ; scan name for a '$'
01 AB 67 59 28 ODB6 540 beql 10$ ; branch if none
59 51 57 C3 ODB6 541 subl3 r7, r1, r9 ; compute size of node name
67 59 28 ODBA 542 movc3 r9, (r7), - ; copy node name string to work area
6B 59 90 ODBF 543 pdvnm_t_node+1(r11)
59 59 D6 ODC2 544 movb r9, pdvnm_t_node(r11) ; store node name size
56 59 C2 ODC4 545 incl r9 ; get size of node name incl. '$'
57 59 C0 ODC7 546 subl r9, r6 ; adjust input string descriptor to
56 D5 ODCA 547 addl r9, r7 ; remove node name section
50 67 30 83 ODCE 548 10$: tstl r6 ; anything left to work with?
09 50 12 19 ODD2 549 beql 90$ ; branch if no characters left
20 AB 0A A4 ODD9 550 20$: subb3 #a/0/, (r7), r0 ; convert next character to a
20 AB 50 A0 ODD9 551 blss 50$ ; a numeric value and branch to
58 01 C8 ODE1 552 cmpb r0, #9 ; 50$ if not a numeric digit
11 11 ODE4 553 bgtru 50$
13 58 E8 ODE6 554 mulw #10, pdvnm_w_unit(r11) ; scale unit number by ten
50 10 AB 9A ODE9 555 addw r0, pdvnm_w_unit(r11) ; and add new digit
11 AB40 67 90 ODED 556 bisl #flag_m_one_unit, r8 ; set the unit number found flag
10 AB 50 01 81 ODF2 557 brb 66$ ; go do next digit
57 D6 ODF7 558 50$: assume flag_v_one_unit eq 0
D2 56 F5 ODF9 559 blbs r8, 90$ ; branch if unit number already found
05 ODFC 560 movzbl pdvnm_t_ddc(r11), r0 ; get number of characters in dev/ctrl
561 movb (r7), - ; move new character into place
562 ODF2 562 pdvnm_t_ddc+1(r11)[r0]
563 addb3 #1, r0, pdvnm_t_ddc(r11) ; store new character count
564 66$: incl r7 ; move string pointer
565 sobgtr r6, 20$ ; reduce character count and branch
566 if characters still left to process
567 90$: rsb

```



```
0DFD 569 .sbtcl show_ddbs -- display device data blocks (DDBs)
0DFD 570 :---
0DFD 571 :
0DFD 572 show_ddbs
0DFD 573 :
0DFD 574 This routine displays all active DDB's associated
0DFD 575 with a specified generic device name.
0DFD 576 :
0DFD 577 Inputs:
0DFD 578 :
0DFD 579 AP = pointer to TPARSE block
0DFD 580 :
0DFD 581 :---
0DFD 582 .save
000008D2 583 .psect literals
08D2 584
08D2 585 found_dpt:
000008DA'00000008' 08D2 586 .address 8, 10$
08DA 587 10$: string <_!XL !10<!AC!AC!> !6AD!+!+ !10AC !XL !XW>
0915 588
0915 589 no_dpt:
0000091D'00000006' 0915 590 .address 6, 10$
091D 591 10$: string <_!XL !10<!AC!AC!> !6AD!+!+ !10AC>
094F 592
00000DFD 593 .restore
0DFD 594
0FFC 0DFD 595 show_ddbs:
0DFD 596 .word ^m<r2,r3,r4,r5,r6,r7,r8,r9,r10,r11>
0DFD 597
0DFD 598 skip page
0E06 599 print 0,<_!-!-!-!_DDB list>
0E13 600 print 0,<_!-!-!-!_----->
0E20 601 skip 1
0E29 602 print 0,<_! Address Controller ACP Driver DPT DPT size
0E36 603 print 0,<_! -----
0E43 604 skip 1
5B D4 0E4C 605 clrl r11 ; make get_ddb initialize
0E4E 606
0084 30 0E4E 607 10$: bsbw get_ddb ; find next DDB
62 50 E9 0E51 608 blbc r0,-90$ ; end of DDB list
54 00000915'EF 7D 0E54 609 movq no_dpt, r4 ; assume no DPT will be found
5A 10 0E58 610 bsbb find_dpt ; locate dpt; r7 = local dpt; r8 = address
0D 50 E9 0E5D 611 blbc r0, T7$ ; branch if not found
54 000008D2'EF 7D 0E60 612 movq found_dpt, r4 ; show that DPT was found
7E 08 A7 3C 0E67 613 movzwl dpt$w_size(r7), -(sp) ; length of DPT
58 DD 0E6B 614 pushl r8 ; address of DPT
24 A6 DF 0E6D 615 17$: pushal ddb$t_drvname(r6) ; address of driver name
7E 7C 0E70 616 clrq -(sp) ; allocate 2 longwords for ACP name
6E DF 0E72 617 pushal (sp)
7E D4 0E74 618 clrl -(sp) ; assume no ACP name for this DDB
50 10 A6 FF000000 8F CB 0E76 619 bicl3 #^xff000000, - ; obtain ACP name for this DDB
0E7F 620 ddb$l_acpd(r6), r0
0E7F 621 beql 30$ ; branch if no ACP name in this DDB
08 AE 50 D0 0E81 622 movl r0, 8(sp) ; put name in the working string
6E 06 D0 0E85 623 movl #6, (sp) ; set length of ACP name
0B AE 00505158 8F D0 0E88 624 movl #^a'XQP', 11(sp) ; assume ACP is really an XQP
50 00313146 8F D1 0E90 625 cmpl #^a'F11', r0 ; is it an XQP?
```

DEVICE
V04-000

Display device data structures
show_ddbs -- display device data blocks

H 12

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 15
(8)

```
OB AE 00504341 08 13 0E97 626      beql 30$      ; branch if its an XQP
          8F D0 0E99 627      movl #^a'ACP', 11(sp) ; else, change it to an ACP
          14 A6 DF 0EA1 628 30$: pushal ddb$t_name(r6) ; generic device name for controller
          44 AB 9F 0EA4 629      pushab sb$t_nodename(r11) ; node name
          59 DD 0EA7 630      pushl r9 ; actual address of DDB
          98 11 0EA9 631      printd r4 (r5) ; print a line
          04 0EB4 632      brb 10$ ; loop till out of DDBs
          04 0EB6 633 90$: ret ; then return
```

```

0EB7 635 ;
0EB7 636 ; Subroutine to locate the DPT corresponding to the current
0EB7 637 ; DDB.
0EB7 638 ;
0EB7 639 find_dpt:
57 00000439'EF 3C BB 0EB7 640 pushr #^m<r2,r3,r4,r5>
2F 50 9E 0EB9 641 movab dpt,r7
58 67 D0 0EC0 642 trymem @ioc$gl_dptlist,dpt$l_flink(r7) ; set address of first DPT
00000000'EF 58 D1 0ED0 643 blbc r0,90$ ; branch if error
21 13 D1 0ED3 644 10$: movl dpt$l_flink(r7),r8 ; skip to next DPT
50 20 A7 50 29 0ED6 645 cmpl r8,ioc$gl_dptlist ; check if back to listhead
25 A6 21 A7 50 12 0EDD 646 beql 80$ ; branch if end of list
50 01 D0 0EDF 647 trymem (r8),(r7),#dpt$length ; read the entire dpt
02 11 D0 0EEC 648 blbc r0,90$ ; branch if error
50 3C BA 0EEF 649 movzbl dpt$length(r7),r0 ; get length of dpt driver name
05 0F02 650 cmpl r0,dpt$length(r7),ddb$length ; compare lengths
0F04 651 bneq 10$ ; branch if no match yet
0F04 652 50$: movl #1,r0 ; success
0F04 653 brb 90$
0F04 654 80$: clrl r0 ; not found
0F04 655 90$: popr #^m<r2,r3,r4,r5>
0F04 656 rsb

```

```

OF05 658 .sbttl get_ddb -- locate the next DDB in the I/O database
OF05 659 :---
OF05 660 :
OF05 661 : get_ddb
OF05 662 :
OF05 663 : This routine locates the next DDB in the I/O database. All
OF05 664 : available system blocks are searched. However, if a node name
OF05 665 : is specified, only the system block whose node name matches
OF05 666 : actually has DDBs returned.
OF05 667 :
OF05 668 : Inputs:
OF05 669 :
OF05 670 : r6 - addr of DDB, local storage
OF05 671 : r11 - addr of SB, local storage
OF05 672 : (zero means initialize scan)
OF05 673 :
OF05 674 : Outputs:
OF05 675 :
OF05 676 : r0 - status
OF05 677 : r6 - addr of DDB, local storage
OF05 678 : r9 - SYS VA of DDB
OF05 679 : r11 - addr of SB, local storage
OF05 680 :
OF05 681 :---
OF05 682 :
OF05 683 get_ddb:
5B D5 OF05 684 tstl r11 ; must we initialize?
64 '3 OF07 685 beql 1500$ ; branch if must initialize
OF09 686
59 66 D0 OF09 687 10$: movl ddb$l_link(r6),r9 ; skip to next DDB
61 13 OF0C 688 beql 100$ ; if end of list, go try next SB
OF0E 689 getmem (r9), (r6), - ; read entire DDB
OF0E 690 #ddb$c length
4A 50 E9 OF1F 691 blbc r0, 90$ ; skip if cannot read
57 00000551'EF 9E OF22 692 movab parsed_devnam, r7 ; get parsed device name data base addr.
51 10 A7 9A OF29 693 movzbl pdvnm_t_ddc(r7), r1 ; was generic device specified?
OE 13 OF2D 694 beql 50$ ; branch if not
14 A6 51 91 OF2F 695 cmpb r1, ddb$t_name(r6) ; Is device name big enough?
15 A6 11 A7 51 29 OF33 696 bgtru 10$ ; branch if not
OF35 697 cmpc3 r1, pdvnm_t_ddc+1(r7), -
OF3B 698 ddb$t_name+1(r6)
44 AB 22 A7 90 OF3B 699 bneq 10$ ; loop until end of list
00000000'EF 34 A6 D1 OF3D 700 50$: movb pdvnm_b_nodsz(r7), - ; assume that the node name is
OF42 701 sb$t_nodename(r11) ; required for this DDB
OF4A 702 cmpl ddb$t_sb(r6), - ; is this the local node?
OF4A 703 scs$ga_localsb
51 04 A6 D0 OF4A 704 bneq 70$ ; no, node name is required
51 40 A6 D0 OF4C 705 movl ddb$l_ucb(r6), r1 ; for the local node, we want to
11 13 OF50 706 bneq 53$ ; show a node name if and only if
03 51 OE E0 OF52 707 movl ddb$l_dp_ucb(r6), r1 ; this is a file oriented device
44 AB 94 OF56 708 beql 70$ ; if we cannot tell, show the node name
50 01 D0 OF58 709 53$: getmem ucb$l_devchar(r1) ; else test for a file oriented device
OF62 710 bbs #dev$V_fod, r1, 70$ ; using device characteristics flag
OF66 711 clrb sb$t_nodename(r11) ; if not fod, vanish node name
OF69 712 70$: movl #1,r0 ; set success
OF6C 713 90$: rsb
52 11 OF6D 714 90$: brb 500$ ; branch assist

```

```

00000000'EF 5A 50 D4 0F6F 715
00000000'EF 5A 6B D0 0F6F 716 ;
00000000'EF 5A 13 D1 0F6F 717 ; move to next SB
00000000'EF 5A 13 D1 0F6F 718 ;
00000000'EF 5A 13 D1 0F6F 719 ;
00000000'EF 5A 13 D1 0F6F 720 100$: clrl r0 ; Set for failure
00000000'EF 5A 13 D1 0F71 721 movl sb$l_flink(r11), r10 ; Get next block
00000000'EF 5A 13 D1 0F74 722 cmpl r10, scs$gq_config ; Reached end of queue?
00000000'EF 5A 13 D1 0F7B 723 beql 90$ ; yes
00000000'EF 5A 13 D1 0F7D 724 getmem (r10), (r11), - ; Pick up system block
00000000'EF 5A 13 D1 0F7D 725 #sb$c_length
00000000'EF 5A 13 D1 0F8E 726 blbc r0, 90$ ; exit if broken
00000000'EF 5A 13 D1 0F91 727 movl sb$l_ddb(r11), -
00000000'EF 5A 13 D1 0F94 728 ddb$l_link(r6) ; set address of first DDB
00000000'EF 5A 13 D1 0F95 729 movab parsed_devnam, r10 ; get parsed device name data base addr.
00000000'EF 5A 13 D1 0F9C 730 movzbl sb$t_nodename(r11), r0 ; get size of node name
00000000'EF 5A 13 D1 0FA0 731 beql 120$ ; branch if no node name
00000000'EF 5A 13 D1 0FA2 732 movb #^a/$/, - ; append '$' to the node name
00000000'EF 5A 13 D1 0FA7 733 sb$t_nodename+1(r11)[r0]
00000000'EF 5A 13 D1 0FA7 734 addb3 #1, r0, pdvnm_b_nodesz(r10) ; store new node name size
00000000'EF 5A 13 D1 0FAC 735 120$: movzbl pdvnm_t_node(r10), r5 ; pick up requested node name lenght
00000000'EF 5A 13 D1 0FAF 736 beql 130$ ; there is none, go scan DDB chain
00000000'EF 5A 13 D1 0FB1 737 cmpb r5, r0 ; do length match?
00000000'EF 5A 13 D1 0FB4 738 bneq 100$ ; no, this cannot be it
00000000'EF 5A 13 D1 0FB6 739 cmpc3 r5, - ; do names match?
00000000'EF 5A 13 D1 0FBC 740 pdvnm_t_node+1(r10), -
00000000'EF 5A 13 D1 0FBC 741 sb$t_nodename+1(r11)
00000000'EF 5A 13 D1 0FBC 742 bneq 100$ ; no, this cannot be it
00000000'EF 5A 13 D1 0FBE 743 130$: brw 10$ ; go scan the DDB chain
00000000'EF 5A 13 D1 0FC1 744
00000000'EF 5A 13 D1 0FC1 745 ;
00000000'EF 5A 13 D1 0FC1 746 ; initialize I/O database scan
00000000'EF 5A 13 D1 0FC1 747 ;
00000000'EF 5A 13 D1 0FC1 748
00000000'EF 5A 13 D1 0FC1 749 500$: movab sb, r11 ; pickup local SB storage address
00000000'EF 5A 13 D1 0FC8 750 movab ddb, r6 ; pickup local DDB storage address
00000000'EF 5A 13 D1 0FCF 751 getmem @scs$gq_config, - ; initialize next SB pointer
00000000'EF 5A 13 D1 0FCF 752 sb$l_flink(r11)
00000000'EF 5A 13 D1 0FDF 753 brb 100$ ; link to next SB

```

```

OFE1 755 .sbtll show_controller, Display controller information
OFE1 756 :---
OFE1 757 :
OFE1 758 show_controller
OFE1 759 :
OFE1 760 Display all information related to the controller
OFE1 761 device associated with each generic device name.
OFE1 762 :
OFE1 763 Inputs:
OFE1 764 :
OFE1 765 4(ap) = Address of DDB in local storage
OFE1 766 8(ap) = Address of UCB in local storage
OFE1 767 12(ap) = Address of node name in local storage
OFE1 768 16(ap) = SVA of DDB
OFE1 769 :
OFE1 770 :---
OFE1 771 :
OFE1 772 show_controller:
OFE1 773 .word ^m<r2,r3,r4,r5,r6,r7>
54 52 04 AC 7D OFE3 774 movq 4(ap),r2 ; get address of DDB,UCB
00000000'EF 9E OFE7 775 movab buffer,r4
OFE1 776 :
OFE1 777 ; begin with controller heading
OFE1 778 :
OFE1 779 skip page
14 A2 DF OFF5 780 pushal ddb$t_name(r2) ; generic controller name
OC AC DD OFF8 781 pushl 12(ap)
OFE1 782 print 2,<Controller: !AC!AC>
6E 14 A2 DD 1008 783 pushl #12
6E OC BC 80 100A 784 addb ddb$t_name(r2), (sp)
100E 785 addb @12(ap), (sp)
1012 786 print 1,<!-->
101F 787 skip 1
00000000'EF 34 A2 91 1028 788 :
08 13 1030 789 cmpb ddb$l_sb(r2), scs$ga_localsb ; skip this stuff if
34 A2 DD 1032 790 beql skip_sb ; this is the local SB
17D8'CF 01 FB 1035 791 pushl ddb$l_sb(r2) ; else, display SB and
103A 792 calls #1, w$show_system_block ; related information
103A 793 :
103A 794 skip_sb:
104C 795 getmem @16(ap), (r4), #ddb$sk_length ; copy DDB to local mem.
1050 796 retiferr
10  AC DD 1068 797 ensure 6
1068 798 pushl 16(ap)
1078 799 print 1,<!-- Device Data Block (DDB) !XL --->
1081 800 skip 1
1081 801 print_columns -
1081 802 buffer, 16(ap), -
1081 803 ddb_column_1, ddb_column_2, ddb_column_3
10A3 804 skip 1
10AC 805 :
10AC 806 getmem @ucb$l_crb(r3), (r4), #crb$sk_length ; get primary CRB
10BE 807 retiferr
10C2 808 ensure 8
24 A3 DD 10DA 809 pushl ucb$l_crb(r3)
10DD 810 print 1,<!-- Primary Channel Request Block (CRB) !XL --->
10EA 811 skip 1

```

```
00000578'EF  40 A3  90 10F3  812      movb    ucb$b_devclass(r3), crb_devclass      ; setup device info.
                                10FB  813      print_columns =
                                10FB  814      buffer, ucb$l_crb(r3), -      ; output CRB columns
                                10FB  815      crb_column_1, crb_column_2, crb_column_3
50  24 A3  24  C1 111D  816      addl3    #crb$l_intd, ucb$l_crb(r3), r0
                                1122  817      print_columns =
                                1122  818      buffer+crb$l_intd, r0, -      ; output VEC columns
                                1122  819      vec_column_1, vec_column_2, vec_column_3
                                1143  820      skip      1
                                114C  821
57  20 A4  D0 114C  822      movl     crb$l_link(r4), r7      ; link to second. CRB
                                03  12 1150  823      bneq     10$
                                0093 31 1152  824      brw      skip_second_crb      ; branch if none
                                1155  825 10$: getmem    (r7), (r4), #crb$l_length      ; get secondary CRB
                                1166  826      retiferr
                                116A  827      ensure    8
57  DD 1182  828      pushl    r7
                                1184  829      print     1, <!-- Secondary Channel Request Block (CRB) !XL --->
                                1191  830      skip      1
                                119A  831      print_columns =
                                119A  832      buffer, r7, -      ; output CRB columns
                                119A  833      crb_column_1, crb_column_2, crb_column_3
57  24  C0 11BB  834      addl2    #crb$l_intd, r7
                                11BE  835      print_columns =
                                11BE  836      buffer+crb$l_intd, r7, -      ; output VEC columns
                                11BE  837      vec_column_1, vec_column_2, vec_column_3
                                11DF  838      skip      1
                                11E8  839
00000000'EF  34 A2  D1 11E8  840      skip_second_crb:
                                03  13 11F0  841      cmpb     ddb$l_sb(r2), scs$ga_localsb      ; is this a local dev.?
                                0080 31 11F2  842      beql     10$
57  24 A3  2C  C1 11F5  843      brw      display_ddt      ; if so, skip IDB etc.
                                11FA  844 10$: addl3    #<crb$l_intd+vec$l_idb>, -      ; locate address of
                                11FA  845      ucb$l_crb(r3), r7      ; primary IDB
                                1203  846      getmem    (r7)      ; get that address
57  51  D0 1207  847      retiferr
                                120A  848      movl     r1, r7      ; save IDB address
                                1217  849      getmem    (r7), (r4), #idb$l_length      ; copy IDB to local mem.
                                121B  850      retiferr
57  DD 1233  851      ensure    4
                                1235  852      pushl    r7
                                1242  853      print     1, <!-- Interrupt Data Block (IDB) !XL --->
                                1248  854      skip      1
                                1248  855      print_columns =
                                1248  856      buffer, r7, -
                                1248  857      idb_column_1, idb_column_2, idb_column_3
                                126C  858      skip      1
                                1275  859
0088 C3  DD 1275  860      display_ddt:
                                1275  861      getmem    auct$l_ddt(r3), (r4), #ddt$l_length      ; copy DDT to local mem.
                                1284  862      retiferr
                                1288  863      ensure    6
                                12A0  864      pushl    ucb$l_ddt(r3)
                                12A4  865      print     1, <!-- Driver Dispatch Table (DDT) !XL --->
                                12B1  866      skip      1
                                12BA  867      print_columns =
                                12BA  868      buffer, ucb$l_ddt(r3), -
```

DEVICE
V04-000

Display device data structures N 12 16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
show_controller, Display controller info 5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1
12BA 869 ddt_column_1, ddt_column_2, ddt_column_3
12DD 870
04 12DD 871 ret

Page 21
(10)

DE
VO


```

12DE 873      .sbtll show_controller tables & action routines
12DE 874
12DE 875      ; The following are all PRINT_COLUMNS action routines for the show
12DE 876      ; controller displays.
12DE 877
12DE 878      Action Routine Inputs:
12DE 879
12DE 880      R2      value from the COLUMN_LIST entry
12DE 881      R5      size of value section for this item
12DE 882      R7      address of a descriptor for a scratch string in
12DE 883      which the FAO converted value is to be returned
12DE 884      R11     base address of the local UCB copy
12DE 885
12DE 886      Action Routine Outputs:
12DE 887
12DE 888      R0      status
12DE 889      lbs ==> use this entry
12DE 890      lbc ==> skip this entry
12DE 891      R1 - R5 scratch
12DE 892      all other registers must be preserved
12DE 893
12DE 894      ;
12DE 895      ; FAO control strings, etc. used by the action routines
12DE 896      ;
12DE 897
12DE 898      .save
00000B47 899      .psect literals
0B47 900
0B47 901 vec_fao_datapath:
0B47 902      string <!UB!AC!AC>
0B58 903
0B58 904 vec_fao_mapreg:
0B58 905      string <!UB(!UB)!AC>
0B6B 906
0B6B 907 vec_lwae:
45 41 57 4C 20 00' 0B6B 908      .ascic / LWAE/
05 0B6B
0B71 909
0B71 910 vec_locked:
64 65 6B 63 6F 4C 20 00' 0B71 911      .ascic / Locked/
07 0B71
0B79 912
0B79 913 ddt_return:
6E 72 75 74 65 72 00' 0B79 914      .ascic /return/
06 0B79
0B80 915
000012DE 916      .restore
12DE 917
12DE 918      ;
12DE 919      ; PRINT_COLUMNS tables for DDB display
12DE 920      ;
12DE 921
12DE 922 ddb_column_1:
12DE 923      column_list -
12DE 924      ddb$, 20, 8, 3, <-
12DE 925      <<Driver name>,t_drvname,ac,13,15>,-
12DE 926      <<ACP ident>,ddb_acpd,0,25,3>,-

```

```

12DE 927 <<ACP class>,ddb_acpcls,0>, -
12DE 928 >
131E 929
131E 930 ddb_column_2:
131E 931 column_list -
131E 932 ddb$, 15, 8, 3, <-
131E 933 <<Alloc. class>,l_alloccls,ub>, -
131E 934 <<SB address>,l_sb,xl>, -
131E 935 <<UCB address>,l_ucb,xl>, -
131E 936 >
135E 937 ddb_column_3:
135E 938 column_list -
135E 939 ddb$, 15, 8, 0, <-
135E 940 <<DDT address>,l_ddt,xl>, -
135E 941 <<CONLINK addr.>,l_conlink,xl_neq>, -
135E 942 <<2p UCB addr.>,l_dp_ucb,xl_neq>, -
135E 943 >
139E 944
139E 945 ;*****
139E 946 ddb_acpd:
139E 947 bicl3 #*xff000000, ddb$l_acpd(r11), - ; get ACP descriptor
13A7 948 r2
13A7 949 beql ddb_no_acp ; branch if no ACP info
13A9 950 rotl #8, r2, r2 ; make ACP descriptor into
52 52 08 9C 13A9 951 ; an ASCII string and
52 03 C0 13AD 952 ; push it onto the stack
52 5E D0 13B0 953 ; save ASCII pointer
8E D5 13B2 954 do_column_entry ac ; display ACP type id
05 13C0 955 tsfl (sp)+ ; cleanup stack
50 D4 13C1 956 rsb
05 13C1 957 ddb_no_acp:
13C1 958 clrl r0
13C3 959 rsb
13C4 960
13C4 961 ;*****
13C4 962 ddb_acpcls:
13C4 963 movzbl ddb$b_acpclass(r11), r2 ; get ACP class
13C8 964 beql ddb_no_acp ; branch if none
53 ECC2 CF 9E 13CA 965 movab ddb_acpclass, r3 ; get translate table
00000000 GF 16 13CF 966 jsb g^translate_address ; translate ACP class
52 50 D0 13D5 967 beql 90$ ; branch if translate failed
13DA 968 movl r0, r2 ; setup translated string
13E3 969 do_column_entry ac, jmp ; display translation
13E3 970
13E7 971 90$: movab ddb$b_acpclass(r11), r2 ; else, get class address
13F0 972 do_column_entry ub, jmp ; just display the value
13F0 973
13F0 974 ;
13F0 975 ; PRINT_COLUMNS tables for CRB display
13F0 976 ;
13F0 977 ;
13F0 978
13F0 979 crb_column_1:
13F0 980 column_list -
13F0 981 crb$, 16, 8, 4, <-
13F0 982 <<Reference count>,w_refc,uw>, -
13F0 983 <<Due time>,crb_timeout,crb$l_duetime>, -

```

```

13F0 984 >
1420 985
1420 986 crb_column_2:
1420 987     column_list -
1420 988         crb$, 16, 8, 4, <-
1420 989         <<Wait queue>,<l_wqfl,q2>,<-
1420 990         <<Timeout rout.>,crb_timeout,crb$l_toutrout>,<-
1420 991         >
1450 992
1450 993 crb_column_3:
1450 994     column_list -
1450 995         crb$, 16, 8, 0, <-
1450 996         <<Aux. struct.>,<l_auxstruc,xl_neq>,<-
1450 997         <<Timeout link>,crb_timeout,crb$l_timelink>,<-
1450 998         >
1480 999
1480 1000 *****
1480 1001 crb_timeout:
00000578'EF 42 8F 91 1480 1002     cmpb     #dc$ term, -           ; terminals have a different
1488 1003         crb_devclass           ; timeout scheme
1488 1004         beql     90$, -           ; so don't do them
1C AB D5 148A 1005         tstl     crb$l_toutrout(r11) ; also don't bother unless
148D 1006         beql     90$, -           ; a time out routine specified
52 5B C0 148F 1007         addl     r11, r2      ; get datum address
1492 1008         do_column_entry xl, jmp ; and display it
50 D4 149B 1009 90$:     clrl     r0           ; or don't show anything
O5 149D 1010         rsb
149E 1011
149E 1012         .save
00000578 1013         .psect    sdadata,noexe,wrt
00000000 0578 1014 crb_devclass:
0000 0578 1015         .long     0
0000 149E 1016         .restore
149E 1017
149E 1018 ;
149E 1019 ; PRINT_COLUMNS tables for VEC display
149E 1020 ;
149E 1021
149E 1022 vec_column_1:
149E 1023     column_list -
149E 1024         vec$, 16, 8, 4, <-
149E 1025         <<IDB address>,<l_idb,xl>,<-
149E 1026         <<ADP address>,<l_adp,xl_neq>,<-
149E 1027         <<Unit start rout.>,<l_start,xl_neq>,<-
149E 1028         >
14DE 1029
14DE 1030 vec_column_2:
14DE 1031     column_list -
14DE 1032         vec$, 16, 8, 4, <-
14DE 1033         <<Datapath>,vec_datapath,0,10,14>,<-
14DE 1034         <<Unit init.>,<l_unitinit,xl_neq>,<-
14DE 1035         <<Disc. rout.>,<l_unitdisc,xl_neq>,<-
14DE 1036         >
151E 1037
00000004 151E 1038 vec$l_intser = vec$q_dispatch+4
151E 1039 vec_column_3:
151E 1040     column_list -

```

```

151E 1041      vec$, 16, 8, 0, <-
151E 1042      <<Map reg.>,vec_mapreg,0,11,13>, -
151E 1043      <<Int. service>,_l_intser,xl_neq>, -
151E 1044      <<Ctrl. init.>,_l_initial,xl_neq>, -
151E 1045      >
155E 1046
155E 1047      ;*****
155E 1048      vec_datapath:
155E 1049      bsbb      vec_test_uba      ; is this a UNIBUS?
1560 1050      subl      #<8*16>,-sp      ; make scratch space on stack
1563 1051      movl      sp, r2      ; point to string descriptor
1566 1052      movl      #16, (r2)      ; build string descriptor
1569 1053      movab     8(r2), 4(r2)
156E 1054      movab     null_ascic, r3      ; assume no LWAE
1575 1055      bbc      #vec$v_lwae, -      ; branch if LWAE not on
157A 1056      vec$b_datapath(r11), 10$
157A 1057      movab     vec_lwae, r3      ; else, change assumption
1581 1058      10$:      movab     null_ascic, r4      ; assume no pathlock
1588 1059      bbc      #vec$v_pathlock, -      ; branch if path not locked
158D 1060      vec$b_datapath(r11), 20$
158D 1061      movab     vec_locked, r4      ; else, change assumption
1594 1062      20$:      extzv      #vec$v_datapath, -      ; extract data path number
159A 1063      #vec$s_datapath, -
159A 1064      vec$b_datapath(r11), r1
159A 1065      $fao_s      -
159A 1066      ctrstr = vec_fao_datapath, -      ; convert everything to
159A 1067      outbuf = (r2), -      ; to a string
159A 1068      outlen = (r2), -
159A 1069      p1 = r1, -
159A 1070      p2 = r3, -
159A 1071      p3 = r4
15B1 1072      do_column_entry as      ; put string in column
15BA 1073      addl      #28+16>, sp      ; cleanup stack
15BD 1074      rsb
15BE 1075
15BE 1076
15BE 1077      ;*****
15BE 1078      vec_test_uba:
15BE 1079      movl      vec$l_adp(r11), r0      ; get ADP address
15C2 1080      beql      90$      ; if none, its not a UBA
15C4 1081      getmem     adp$w_adptype(r0)      ; get adapter type
15CE 1082      blbc     r0, 90$      ; if error, its not a UBA
15D1 1083      cmpw     #at$_uba, r1      ; is it a UBA?
15D4 1084      bneq     90$      ; branch if not a UBA
15D6 1085      rsb      ; else, return to caller
15D7 1086      90$:      tstl      (sp)+      ; if not a UBA, return a skip
15D9 1087      clrl      r0      ; this entry status to the
15DB 1088      rsb      ; action routines caller
15DC 1089
15DC 1090      ;*****
15DC 1091      vec_mapreg:
15DC 1092      bsbb      vec_test_uba      ; is this a UBA?
15DE 1093      subl      #<8*16>,-sp      ; make scratch space on stack
15E1 1094      movl      sp, r2      ; point to string descriptor
15E4 1095      movl      #16, (r2)      ; build string descriptor
15E7 1096      movab     8(r2), 4(r2)
15EC 1097      movab     null_ascic, r4      ; assume no map lock

```

```

07 10 AB 0F E1 15F3 1098      bbc      #vec$w_maplock, -      ; branch if no map lock
                                vec$w_mapreg(r11), 10$
53 54 00000B71'EF 9E 15F8 1099      movab   vec_locked, r4      ; else, change assumption
10 AB 0F 00 EF 15FF 1101 10$:      extzv   #vec$w_mapreg, #vec$s_mapreg, - ; extract starting map
                                vec$w_mapreg(r11), r3      ; number
                                sfao_s
                                -
                                ctrstr = vec_fao_mapreg, - ; convert whole mess to a
                                outbuf = (r2), -          ; string
                                outlen = (r2), -
                                p1 = r3, -
                                p2 = vec$b_numreg(r11), -
                                p3 = r4
                                do_column_entry as        ; put string in column
                                addl   #28+16>, sp        ; cleanup stack
                                rsb
SE 18 C0 161D 1110
05 1626 1111
1629 1112
162A 1113
162A 1114
162A 1115 :: PRINT_COLUMNS tables for IDB display
162A 1116 ::
162A 1117
162A 1118 idb_column_1:
162A 1119 column_list -
162A 1120 idb$, 16, 8, 4, <-
162A 1121 <<CSR address>, l_csr, xl>, -
162A 1122 <<Number of units>, w_units, uw>, -
162A 1123 >
165A 1124 idb_column_2:
165A 1125 column_list -
165A 1126 idb$, 16, 8, 4, <-
165A 1127 <<Owner UCB addr.>, l_owner, xl>, -
165A 1128 <<Interrupt vector>, idb_vector, 0, 18, 6>, -
165A 1129 >
168A 1131 idb_column_3:
168A 1132 column_list -
168A 1133 idb$, 16, 8, 0, <-
168A 1134 <<ADP address>, l_adp, xl>, -
168A 1135 >
16AA 1137
16AA 1138 *****
16AA 1139 idb_vector:
50 0B AB 9A 16AA 1140 movzbl idb$b_vector(r11), r0 ; Obtain vector information
12 13 16AE 1141 beql 90$ ; Branch if none present
7E 50 02 78 1680 1142 ashl #2, r0, -(sp) ; Convert vector information
52 5E D0 1684 1143 movl sp, r2 ; Get converted info. addr.
8E D5 1687 1144 do_column_entry ow ; Display information
05 16C0 1145 tsfl (sp)+ ; Cleanup stack
16C2 1146 90$: rsb ; Return to caller
16C3 1147
16C3 1148 :: PRINT_COLUMNS tables for DDT display
16C3 1149 ::
16C3 1150 ::
16C3 1151
16C3 1152 ddt_column_1:
16C3 1153 column_list -
16C3 1154 ddt$, 16, 8, 4, <-

```

```

16C3 1155 <<Errlog buf sz>,w_errorbuf,uw>,-
16C3 1156 <<Start I/O>,ddt_address,ddt$l_start>,-
16C3 1157 <<Alt start I/O>,ddt_address,ddt$l_altstart>,-
16C3 1158 <<Cancel I/O>,ddt_address,ddt$l_cancel>,-
16C3 1159 >
1713 1160 ddt_column_2:
1713 1161 column_list -
1713 1162 ddt$, 16, 8, 4, <-
1713 1163 <<Diag buf sz>,w_diagbuf,uw>,-
1713 1164 <<Register dump>,ddt_address,ddt$l_regdump>,-
1713 1165 <<Unit init>,ddt_address,ddt$l_unitinit>,-
1713 1166 <<Unsol int>,ddt_address,ddt$l_unsolint>,-
1713 1167 >
1763 1168
1763 1169 ddt_column_3:
1763 1170 column_list -
1763 1171 ddt$, 16, 8, 0, <-
1763 1172 <<FDT size>,w_fdtsize,uw>,-
1763 1173 <<FDT address>,l_fdt,xl>,-
1763 1174 <<Mnt verify>,ddt_address,ddt$l_mntver>,-
1763 1175 <<Cloned UCB>,ddt_address,ddt$l_cloneducb>,-
1763 1176 >
1783 1177
1783 1178
1783 1179 ;*****
1783 1180 ddt_address:
1783 1181 addl r11, r2 ; get datum address
1786 1182 cmpl (r2), ioc$return ; is this the RSB routine?
178D 1183 beql 90$ ; branch if RSB routine
178F 1184 do_column_entry xl, jmp ; else, output value
52 00000879'EF 9E 17C8 1185 90$: movab ddt_return, r2 ; for RSB routine, display
17CF 1186 do_column_entry ac, jmp ; 'return'

```

```
17D8 1188 .sbtll show_system_block, show system/path blocks (SB/PB)
17D8 1189 :---
17D8 1190 :
17D8 1191 : show_system_block
17D8 1192 :
17D8 1193 : This routine displays the system and path blocks given
17D8 1194 : the address of the system block.
17D8 1195 :
17D8 1196 : 4(ap) = SVA of the system block of interest
17D8 1197 :---
17D8 1198 :
17D8 1199 show_system_block::
17D8 1200 .word ^m<r2,r3,r4,r5,r6,r7,r8>
54 00000000'EF 01FC 17DA 1201 movab buffer, r4 ; get working buffer
17E1 1202
17E1 1203 : display system block
17E1 1204
17E1 1205 ensure 12
17F9 1206 getmem a4(ap), (r4), #sb$length ; copy SB to local mem.
180B 1207 retiferr
04 AC DD 180F 1208 pushl 4(ap)
44 A4 9F 1812 1209 pushab sb$nodename(r4) ; node name
1815 1210 print 1,<!-- --- !AC System Block (SB) !XL --->
1822 1211 skip 1
182B 1212 print_columns -
182B 1213 buffer, 4(ap), -
182B 1214 sb_column_1, sb_column_2
1847 1215 skip 1
1850 1216
1850 1217
1850 1218 : display each path block
1850 1219
1850 1220 assume pb$length lt 512
64 0C A4 D0 1850 1221 movl sb$_pbfl(r4), pb$_flink(r4) ; init PB scan
1854 1222
1854 1223 pb_loop:
50 04 AC 0C C1 1854 1224 addl3 #sb$_pbfl, 4(ap), r0 ; is there another PB?
50 64 D1 1859 1225 pb$_flink(r4), r0
03 12 185C 1226 cmpl 10$
00B2 31 185E 1227 brw end pb ; branch if no PBs left
58 64 D0 1861 1228 10$: movl pb$_flink(r4), r8 ; save new PB addr.
1864 1229 getmem (r8), (r4), #pb$length ; copy PB to local mem.
1875 1230 retiferr
58 DD 1879 1231 ensure 12
1891 1232 pushl r8
1893 1233 print 1,<!-- --- Path Block (PB) !XL --->
18A0 1234 skip 1
57 5E D0 18A9 1235 movl sp, r7 ; save stack pointer
18AC 1236 alloc 80, r6 ; allocate scratch
7E 44 A4 3C 18BE 1237 movzwl pb$_sts(r4), -(sp) ; push PB STS
E73A CF 9F 18C2 1238 pushab pb$_status ; push bit conv. data
00000000'GF 02 FB 18C6 1239 calls #2, g^translate_bits ; translate PB STS
56 DD 18CD 1240 pushl r6 ; push result
7E 44 A4 3C 18CF 1241 movzwl pb$_sts(r4), -(sp) ; push PB STS
5E 57 D0 18D3 1242 print 2,<!--_Status: !XW !AS> ; output PB STS
18E0 1243 movl r7, sp ; restore stack
18E3 1244 skip 1
```

DEVICE
V04-000

I 13
Display device data structures
show_system_block, show system/path bloc 16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 29
(11)

DE
V0

```
18EC 1245      print_columns -
18EC 1246      buffer, r8, -
18EC 1247      pb_column_1, pb_column_2
FF41 31 1907 1248      skip
1910 1249      brw      pb_loop
1913 1250
1913 1251 end_pb:
04 1913 1252      ret
```



```

1914 1254      .sbttl show_system_block tables & action routines
1914 1255
1914 1256 : The following are all PRINT_COLUMNS action routines for the show
1914 1257 : system/path block displays.
1914 1258
1914 1259 : Action Routine Inputs:
1914 1260 :
1914 1261 : R2      value from the COLUMN_LIST entry
1914 1262 : R5      size of value section for this item
1914 1263 : R7      address of a descriptor for a scratch string in
1914 1264 :         which the FA0 converted value is to be returned
1914 1265 : R11     base address of the local UCB copy
1914 1266 :
1914 1267 : Action Routine Outputs:
1914 1268 :
1914 1269 : R0      status
1914 1270 :         lbs ==> use this entry
1914 1271 :         lbc ==> skip this entry
1914 1272 : R1 - R5  scratch
1914 1273 :         all other registers must be preserved
1914 1274 :
1914 1275 :
1914 1276 : FA0 control strings, etc. used by the action routines
1914 1277 :
1914 1278
1914 1279      .save
00000DEE 1280      .psect literals,exe,nowrt
0DEE 1281
0DEE 1282 sb_fao_6bytes:
0DEE 1283 string <!* !XW!XL>
0E00 1284
0E00 1285 sb_fao_ascic:
0E00 1286 string <!* !#(AC)>
0E12 1287
0E12 1288 cddb_fao:
0E12 1289 string <!* !XL>
0E21 1290
0E21 1291 null_ascic:
00000000 0E21 1292 .long 0
0E25 1293
0E25 1294 maint_ascic:
5F 54 4E 49 41 4D 00' 0E25 1295 .ascic /MAINT_/
06
0E2C 1296
0E2C 1297 cbl_a_ascic:
2D 41 00' 0E2C 1298 .ascic /A-/
02
0E2F 1299
0E2F 1300 cbl_b_ascic:
2D 42 20 00' 0E2F 1301 .ascic / B-/
03
0E2F 1302
0E33 1303 ok_ascic:
4B 4F 00' 0E33 1304 .ascic /OK/
02
0E36 1305
0E36 1306 bad_ascic:

```

```

44 41 42 00' 0E36 1307      .ascic /BAD/
03 0E36
0E3A 1308
0E3A 1309 crossed_ascic:
64 65 58 20 00' 0E3A 1310      .ascic / Xed/
04 0E3A
0E3F 1311
0000 1914 1312      .restore
1914 1313
1914 1314
1914 1315 ; PRINT_COLUMNS tables for SB display
1914 1316
1914 1317
1914 1318 sb_column_1:
1914 1319     column_list -
1914 1320         sb$, 21, 12, 4, < -
1914 1321         <<System ID>,sb_6bytes,sb$b_systemid>, -
1914 1322         <<Max message size>,w_maxmsg,uw>, -
1914 1323         <<Max datagram size>,w_maxdg,uw>, -
1914 1324         <<Local hardware type>,sb_lwchar,sb$t_hwtype,29,4>, -
1914 1325         <<Local hardware vers.>,sb_6bytes,sb$b_hwvers>, -
1914 1326         << >,sb_6bytes,sb$b_hwvers+6>, -
1914 1327         >
1984 1328
00000030 1984 1329 sb$q_swincarn2 = sb$q_swincarn+4
1984 1330 sb_column_2:
1984 1331     column_list -
1984 1332         sb$, 21, 12, 0, < -
1984 1333         <<Local software type>,sb_lwchar,sb$t_swtype,29,4>, -
1984 1334         <<Local software vers.>,sb_lwchar,sb$t_swvers,29,4>, -
1984 1335         <<Local software incarn.>,q_swincarn,xl,25,8>, -
1984 1336         << >,q_swincarn2,xl,25,8>, -
1984 1337         <<SCS poller timeout>,w_timeout,xw>, -
1984 1338         <<SCS poller enable mask>,b_enbmsk,xb,31,2>, -
1984 1339         >
19F4 1340
19F4 1341 ;*****
19F4 1342 sb_6bytes:
53 58 52 C1 19F4 1343     addl3 r2, r11, r3      ; locate storage of interest
55 0C C2 19F8 1344     subl #12, r5      ; get size of filler field
19FB 1345     $fao_s -
19FB 1346     ctrstr = sb_fao_6bytes, -
19FB 1347     outbuf = (r7), -
19FB 1348     outlen = (r7), -
19FB 1349     p1 = r5, -
19FB 1350     p2 = 4(r3), -
19FB 1351     p3 = (r3)
05 1A13 1352     rsb
1A14 1353
1A14 1354 ;*****
53 58 52 C1 1A14 1355 sb_lwchar:
7E 1A18 1356     addl3 r2, r11, r3      ; locate storage of interest
63 95 1A1A 1357     clrl -(sp)      ; make scratch ASCII space
16 13 1A1A 1358     tstb (r3)      ; check for null string
04 DD 1A1E 1359     beql 5$      ; equal, null string
52 5E D0 1A20 1360     pushl #4      ; of the right size
10$ 1361     movl sp, r2      ; save ASCII pointer

```

```
01 A2 63 D0 1A23 1362      movl      (r3), 1(r2)      ; put text in ASCII string
                    1A27 1363      do_column_entry ac      ; convert the ASCII
SE 08 C0 1A30 1364      addl      #22*4>, sp      ; cleanup stack
                    05 1A33 1365      rsb
                    1A34 1366
00 DD 1A34 1367 5$:      pushl      #0
E8 11 1A36 1368          brb        10$
                    1A38 1369
                    1A38 1370      ;
                    1A38 1371      ; PRINT_COLUMNS tables for PB display
                    1A38 1372      ;
                    1A38 1373
                    1A38 1374      pb_column_1:
                    1A38 1375          column_list -
                    1A38 1376              pb$, 21, 12, 4, < -
                    1A38 1377              <<Remote sta. addr.>,sb_6bytes,pb$b_rstation>, -
                    1A38 1378              <<Remote state>,pb_rmtstate,0>, -
                    1A38 1379              <<Remote hardware rev.>,l_rport_rev,xl>, -
                    1A38 1380              <<Remote func. mask>,l_rport_fcñ,xl>, -
                    1A38 1381              <<Reseting port>,b_rst_port,xl>, -
                    1A38 1382              <<Handshake retry cnt.>,w_retry,uw>, -
                    1A38 1383              <<Msg. buf. wait queue>,l_waitqfl,q2>, -
                    1A38 1384              >
                    1AB8 1385
                    1AB8 1386      pb_column_2:
                    1AB8 1387          column_list -
                    1AB8 1388              pb$, 21, 12, 4, < -
                    1AB8 1389              <<Remote port type>,pb_rport_typ,0>, -
                    1AB8 1390              <<Number of data paths>,pb_dualpath,0>, -
                    1AB8 1391              <<Cables state>,pb_cables,0,18,15>, -
                    1AB8 1392              <<Local state>,pb_lclstate,0>, -
                    1AB8 1393              <<Port dev. name>,sb_lwchar,pb$tlport_name,29,4>, -
                    1AB8 1394              <<SCS MSGBUF address>,l_scsmsg,xl>, -
                    1AB8 1395              <<PDT address>,l_pdt,xl>, -
                    1AB8 1396              >
                    1B38 1397
                    1B38 1398      ;*****
                    1B38 1399      pb_rmtstate:
54 00000E21'EF 9E 1B38 1400      movab      null_ascic, r4      ; assume rport not in maint.
                    1B3F 1401          assume      pb$v_maint eq 0      ; state
                    1B3F 1402          blbc      pb$b_rstate(r11), 20$      ; branch if rport not in maint.
54 00000E25'EF 9E 1B43 1403      movab      maint_ascic, r4      ; else, set maintenance flag
                    55 64 A2 1B4A 1404          subw      (r4), r5      ; and reduce the fill count
53 E4E7 CF 9E 1B4D 1405 20$:      movab      pb_rstate, r3      ; get remote state tbl. addr.
52 21 AB 02 01 EF 1B52 1406          extzv      #pb$v_state, #pb$s_state, -      ; extract remote port state
                    1B58 1407              pb$b_rstate(r11), r2      ; information
                    1B58 1408              jsb      g^translate_address      ; convert it to ASCII pointer
                    1B5E 1409              beql      90$      ; branch if translation failed
                    55 60 82 1B60 1410          subb      (r0), r5      ; reduce the fill count
                    1B63 1411          $fao_s -
                    1B63 1412              ctrstr = sb_fao_ascic, -
                    1B63 1413              outbuf = (r7), =
                    1B63 1414              outlen = (r7), -
                    1B63 1415              p1 = r5, -
                    1B63 1416              p2 = #2, -
                    1B63 1417              p3 = r4, -
                    1B63 1418              p4 = r0
```

```

52 21 AB 05 1B7C 1419      rsb
9E 1B7D 1420 90$:      movab  pb$b_rstate(r11), r2      ; if cannot convert remote
1B81 1421      do_column_entry xb, jmp                ; status then display value
1B8A 1422      ;*****
1B8A 1423      pb_rport_typ:
1B8A 1424      movab  pb_rport_type, r3                ; get port type conversion
1B8F 1425      assume pb$v_port_typ eq 0
1B8F 1426      assume pb$s_port_typ eq 31
1B8F 1427      bicl3  #^x80000000, -                    ; get remote port type value
1B98 1428      pb$l_rport_typ(r11), r2
1B98 1429      jsb    g^translate_address                ; translate port type
1B98 1430      beql   90$                                ; branch if translation failed
1B9E 1431      beql   90$                                ; setup string for display
1BA0 1432      movl   r0, r2                            ; display translated string
1BA3 1433      do_column_entry ac, jmp
1BAC 1434
1BAC 1435 90$:      pushl  r2                            ; else, display just the port
1BAE 1436      movl   sp, r2                            ; type value
1BB1 1437      do_column_entry xl
1BBA 1438      tsfl   (sp)+                            ; cleanup stack
1BBC 1439      rsb
1BBD 1440
1BBD 1441      ;*****
1BBD 1442      pb_dualpath:
1BBD 1443      assume pb$m_dualpath eq <^x80000000>
1BBD 1444      extzv   #pb$v_dualpath, #1, -                ; get paths flag for remote port
1BC3 1445      pb$l_rport_typ(r11), r2
1BC3 1446      addl3  #1, r2, -(sp)                        ; add one (there's at least one)
1BC7 1447      movl   sp, r2                            ; get value pointer
1BCA 1448      do_column_entry ul                        ; display value
1BD3 1449      tsfl   (sp)+                            ; cleanup stack
1BD5 1450      rsb
1BD6 1451
1BD6 1452      ;*****
1BD6 1453      pb_cables:
1BD6 1454      assume pb$v_cur_ps eq 0
1BD6 1455      movl   #3, r4                                ; assume single path port
1BD9 1456 10$:      pushab null_ascic
1BDF 1457      sobgtr r4, 10$
1BE2 1458
1BE2 1459      subl   #4, r5                                ; adjust fill for path A
1BE5 1460      pushab ok_ascic                            ; assume path A is ok
1BEB 1461      blbs   pb$b_p0_sts(r11), 25$                ; branch if path A is ok
1BEF 1462      movab  bad_cic, (sp)                        ; else, change path A to bad
1BF6 1463      decl   r5                                ; adjust fill for bad path
1BF8 1464 25$:      pushab cbl_a_ascic                    ; insert "A-"
1BFE 1465
1BFE 1466      assume pb$m_dualpath eq <^x80000000>
1BFE 1467      tstl   pb$l_rport_typ(r11)                    ; is this a dual pathed port?
1C01 1468      bgeq   40$                                ; branch if not dual pathed
1C03 1469      subl   #5, r5                                ; adjust fill for path B
1C06 1470      movab  ok_ascic, 12(sp)                    ; assume path B is ok
1C0E 1471      blbs   pb$b_p1_sts(r11), 33$                ; branch if path B is ok
1C12 1472      movab  bad_ascic, 12(sp)                    ; else, change path B to bad
1C1A 1473      decl   r5                                ; adjust fill for bad path
1C1C 1474 33$:      movab  cbl_b_ascic, 8(sp)                ; add "B-"
1C24 1475      assume pb$v_cur_cbl eq 0
```

DEVICE
V04-000

Display device data structures
show_system_block tables & action routines

N 13

16-SEP-1984 01:26:37
5-SEP-1984 03:32:17

VAX/VMS Macro V04-00
[SDA.SRC]DEVICE.MAR;1

Page 34
(11)

```
10 AE 0B 28 AB E8 1C24 1476 blbs pb$b_cbl_sts(r11), 40$ ; branch if cables not crossed
      00000E3A'EF 9E 1C28 1477 movab crossed_ascic, 16(sp) ; else, add crossed cables flag
      55 04 C2 1C30 1478 subl #4, r5 ; and adjust fill count
      05 DD 1C33 1479 ;
      55 DD 1C33 1480 40$: pushl #5 ; set number of ASCICs
      54 5E DD 1C35 1481 pushl r5 ; set fill count
      DO 1C37 1482 movl sp, r4 ; get parameter list pointer
      1C3A 1483 $faol_s -
      1C3A 1484 ctrstr = sb_fao_ascic, -
      1C3A 1485 outbuf = (r7), =
      1C3A 1486 outlen = (r7), -
      1C3A 1487 prmlst = (r4)
      5E 1C 1C40 1488 addl #<7*4>, sp ; cleanup stack
      05 1C50 1489 rsb
      1C51 1490
      1C51 1491 ;*****
      1C51 1492 pb_lclstate:
      53 E3BB CF 9E 1C51 1493 movab pb_state, r3 ; get port state conversion
      1C56 1494 assume pb$w_port_typ eq 0
      52 12 AB 3C 1C56 1495 movzwl pb$w_state(r11), r2 ; get local port state
      00000000'GF 16 1C5A 1496 jsb g^translate_address ; translate port state
      0C 13 1C60 1497 beql 90$ ; branch if translation failed
      52 50 DO 1C62 1498 movl r0, r2 ; setup string for display
      1C65 1499 do_column_entry ac, jmp ; display trans. string
      1C6E 1500
      52 12 AB 9E 1C6E 1501 90$: movab pb$w_state(r11), r2 ; else, display just the port
      1C72 1502 do_column_entry xw, jmp ; state value
```

```
1C7B 1504 .sbtll show_ucb, show unit control block (UCB)
1C7B 1505 :---
1C7B 1506 :
1C7B 1507 show_ucb
1C7B 1508
1C7B 1509 This routine shows the unit control block associated
1C7B 1510 with a device.
1C7B 1511
1C7B 1512
1C7B 1513 4(ap) = address of DDB in local storage
1C7B 1514 8(ap) = address of UCB in local storage
1C7B 1515 12(ap)= actual address of UCB
1C7B 1516 16(ap)= address of nodename in local storage
1C7B 1517 20(ap)= flags longword
1C7B 1518 :---
1C7B 1519 :
1C7B 1520
1C7B 1521 show_ucb:
OFFC 1C7B 1522 .word ^m<r2,r3,r4,r5,r6,r7,r8,r9,r10,r11>
1C7D 1523
1C7D 1524 ensure 24
1C95 1525 pushl 12(ap) ; push virtual address of UCB
1C98 1526
54 08 AC D0 1C98 1527 movl 8(ap), r4 ; get local address of UCB
00001160'EF 9F 1C9C 1528 pushab unknown ; assume the device will be unknown
52 40 A4 9A 1CA2 1529 movzbl ucb$b_devclass(r4), r2 ; get device class value
53 E5F6 CF 9E 1CA6 1530 movab device_class, r3 ; get conversion table
00000000'GF 16 1CAB 1531 jsb g^translate_address ; get address of device type table
12 13 1CB1 1532 beql 90$ ; branch if no class match
52 41 A4 9A 1CB3 1533 movzbl ucb$b_devtype(r4), r2 ; get device type value
53 50 D0 1CB7 1534 movl r0, r3 ; get table address picked above
00000000'GF 16 1CBA 1535 jsb g^translate_address ; get device type ASCII address
03 13 1CC0 1536 beql 90$ ; branch if no device type matches
6E 50 D0 1CC2 1537 movl r0, (sp) ; else replace unknown with devtype
52 04 AC 7D 1CC5 1538 90$: movq 4(ap), r2 ; get DDB and UCB addresses
1CC9 1539
5A 00001065'EF 7D 1CC9 1540 movq one_path, r10 ; assume a single path device which
1CD0 1541 ; is not a virtual terminal
1CD0 1542
40 A3 42 8F 91 1CD0 1543 cmpb #dc$ term, - ; is this a terminal?
1CD5 1544 ucb$b_devclass(r3)
1CD5 1545 bneq 200$ ; branch if not a terminal
54 00A0 C3 D0 1CD7 1546 movl ucb$l_tl_phyucb(r3), r4 ; is this a virtual terminal?
3F 13 1CDC 1547 beql 7777$ ; branch if not a virtual terminal
OC AC 54 D1 1CDE 1548 cmpl r4, 12(ap) ; does virt. term. equal phy. term.?
39 13 1CE2 1549 beql 7777$ ; if yes, then this not a virtual term.
5A 0000111F'EF 7D 1CE4 1550 movq virtual_terminal, r10 ; it is a virtual terminal
1CEB 1551 getmem ucb$w_unit(r4) ; get physical terminal's unit number
7E 51 3C 1CF5 1552 movzwl r1, -(sp) ; push than unit number
55 000000B5'EF 9E 1CF8 1553 movab ddb 2p, r5 ; get work space for phy. DDB copy
1CFF 1554 getmem ucb$l_ddb(r4) ; get address of DDB for phy. UCB
1D09 1555 getmem (r1), -(r5), - ; get local copy of physical DDB
1D09 1556 #ddb$k_length
14 A5 9F 1D1A 1557 pushab ddb$t_name(r5) ; push address of phy. device name
00A4 31 1D1D 1558 7777$: brw ; go setup virtual terminal name
1D20 1559 ; (this is also a branch assist)
1D20 1560
```

```
3C A3 10 D3 1D20 1561 200$: bitl #dev$u_2p, - ; dual path device?
                                1D24 1562 ucb$u_devchar2(r3)
                                F7 13 1D24 1563 beql 7777$ ; branch if not dual path
                                1D26 1564
5A 0000109B'EF 7D 1D26 1565 movq this_primary, r10 ; assume this path is primary
59 00000060'EF 9E 1D2D 1566 movab nodnam_2p, r9 ; get node name workarea address
54 00A8 C3 DC 1D34 1567 movl ucb$u_dp_altucb(r3), r4 ; is there a local path?
1B 12 1D39 1568 bneq local_2p_device ; branch if local path
                                1D3B 1569
                                1D3B 1570 ; both paths through the class driver
                                7E 54 A3 3C 1D3B 1571 movzwl ucb$u_unit(r3), -(sp) ; push secondary unit number
                                55 00A0 C3 D0 1D3F 1572 movl ucb$u_dp_ddb(r3), r5 ; get secondary DDB address
33 14 AC 01 E1 1D44 1573 bbc #flag_v_alt_path, - ; if scanning primary DDB chain,
                                1D49 1574 20(ap), process_2p_ddb ; go join common code
5A 55 28 A3 D0 1D49 1575 movl ucb$u_ddb(r3), r5 ; else, other DDB is primary DDB
000010DD'EF 7D 1D4D 1576 movq this_secondary, r10 ; and this is the secondary path
26 11 1D54 1577 brb process_2p_ddb ; go to common other path code
                                1D56 1578
                                1D56 1579 local_2p_device: ; only one path through the class driver
                                7E 51 3C 1D60 1581 getmem ucb$u_unit(r4) ; get other path unit number
                                1D63 1582 movzwl r1, -(sp) ; push other path unit number
                                55 51 D0 1D6D 1583 getmem ucb$u_ddb(r4) ; get other path ddb address
07 3C A3 03 E1 1D70 1584 movl r1, r5 ; save ddb address in right place
                                1D75 1585 bbc #dev$u_cdp, - ; branch if the path whose UCB is in
                                1D75 1586 ucb$u_devchar2(r3), - ; r3 is the primary path
5A 000010DD'EF 7D 1D75 1587 movq this_secondary, r10 ; else indicate that first name is
                                1D7C 1588 the secondary path
                                1D7C 1589 process_2p_ddb:
54 000000B5'EF 9E 1D7C 1590 movab ddb_2p, r4 ; get workarea address for 2p DDB
                                1D83 1591 getmem (r5), (r4), - ; pickup secondary DDB
                                1D83 1592 #ddb$u_length
                                59 00000060'EF 9F 1D94 1593 pushab ddb$u_name(r4) ; push address of secondary device name
50 34 A4 00000044 8F C1 1D97 1594 movab nodnam_2p, r9 ; get workarea address for 2p node name
                                1D9E 1595 addl3 #sb$u_nodename, - ; locate secondary node name
                                1DA7 1596 ddb$u_sb(r4), r0
                                1DA7 1597 getmem (r0), -(r9), - ; pickup secondary node name
                                1DA7 1598 #sb$u_nodename
                                51 51 9A 1DB4 1599 movzbl r1, r1 ; convert byte count to long word
                                0B 13 1DB7 1600 beql setup_primary ; don't add '$' to null node name
                                51 D6 1DB9 1601 incl r1 ; add one for '$'
                                69 51 90 1DBB 1602 movb r1, (r9) ; store count in ASCII string
6941 24 90 1DBE 1603 movb #^a/$/, (r9)[r1] ; store '$' in string
                                59 DD 1DC2 1604 pushl r9 ; push node name pointer
                                1DC4 1605
                                1DC4 1606 setup_primary:
                                54 A3 DD 1DC4 1607 pushl ucb$u_unit(r3) ; unit number
                                14 A2 DF 1DC7 1608 pushal ddb$u_name(r2) ; generic controller name
                                10 AC DD 1DCA 1609 pushl 16(ap) ; address of nodename
                                1DCD 1610 printd r10, (r11) ; print device name and UCB
                                1DD8 1611 skip 1
                                5B 5E D0 1DE1 1612 movl sp, r11 ; save pre-allocation stack pointer
                                1DE4 1613 alloc 80, r4 ; allocate an output buffer
                                64 A3 DD 1DF6 1614 pushl ucb$u_sts(r3) ; push device status value
                                E2BB CF 9F 1DF9 1615 pushab unit_status ; bit definition table
00000000'EF 02 FB 1DFD 1616 calls #2, translate_bits ; translate bits into string
                                54 DD 1E04 1617 pushl r4 ; result string
```

```

        64 A3 DD 1E06 1618      pushl   ucb$l_sts(r3)      ; push device status value
        1E09 1619      print   2,<Device status: !XL !AS>
        64 50 8F 9A 1E16 1620      movzbl  #80,(r4)      ; refresh output buffer descriptor
        38 A3 DD 1E1A 1621      pushl   ucb$l_devchar(r3)  ; push device characteristics one
        E33F CF 9F 1E1D 1622      pushab  device_char      ; setup bit definition table
00000000'EF 02 FB 1E21 1623      calls   #2,translate_bits ; translate bits into string
        54 DD 1E28 1624      pushl   r4      ; push result string
        38 A3 DD 1E2A 1625      pushl   ucb$l_devchar(r3)  ; push device characteristics one
        1E2D 1626      print   2,<Characteristics: !XL !AS>
        64 50 8F 9A 1E3A 1627      movzbl  #80,(r4)      ; refresh output buffer descriptor
        3C A3 DD 1E3E 1628      pushl   ucb$l_devchar2(r3) ; push device characteristics two
        E403 CF 9F 1E41 1629      pushab  device_char_2    ; setup bit definition table
00000000'EF 02 FB 1E45 1630      calls   #2,translate_bits ; translate bits into string
        54 DD 1E4C 1631      pushl   r4      ; push result string
        3C A3 DD 1E4E 1632      pushl   ucb$l_devchar2(r3) ; push device characteristics two
        1E51 1633      print   2,< !XL !AS>
        5E 5B D0 1E5E 1634      movl    r11,sp      ; restore stack pointer
        1E61 1635      skip     1
        1E6A 1636      define_ucb_symbols:
        1E6A 1637      .enable lsb
        1E6A 1638      make_symbol UCB, 12(ap)
        1E80 1640      make_symbol SB, ddb$l_sb(r2)
        1E96 1641      make_symbol ORB, ucb$l_orb(r3)
        1EAC 1642      make_symbol DDB, ucb$l_ddb(r3)
        1EC2 1643      make_symbol DDT, ucb$l_ddt(r3)
        1ED9 1644      make_symbol CRB, ucb$l_crb(r3)
        60 A3 D5 1EEF 1645      tstl    ucb$l_amb(r3)
        16 13 1EF2 1646      beql     10$
        1EF4 1647      make_symbol AMB, ucb$l_amb(r3)
        16 64 A3 08 E1 1FOA 1648 10$:      bbc     #ucb$vb_sy,ucb$l_sts(r3), 20$
        1F0F 1649      make_symbol IRP, ucb$l_irp(r3)
        1F25 1650 20$:
        1F25 1651      .disable lsb
        1F25 1652
        1F25 1653      do_ucb_columns:
0000057C'EF 04 AC D0 1F25 1654      movl    4(ap),ucb_ddb      ; setup local DDB copy address
        1F2D 1655      print_columns -
        1F2D 1656      @8(ap), 12(ap), -
        1F2D 1657      ucb_column_1, ucb_column_2, ucb_column_3
        7E 08 AC 7D 1F4C 1658      movq    8(ap),-(sp)      ; push local,real address of UCB
        25 3C A3 05 E1 1F50 1659      bbc     #dev$vb_mscp,ucb$l_devchar2(r3), 30$ ; check to see if mscp ser
00000575'EF 00 B0 1F55 1660      movw    #0,flag_2nd_cddb ; initialize flag to zero for primary
        56 00BC C3 D0 1F5C 1661      movl    ucb$l_cddb(r3),r6 ; pass the address of the cddb by reg. 6
0000313C'EF 63 FA 1F61 1662      callg   (r3),show_cddb ; Display class driver data block
        00000575'EF B6 1F68 1663      incw    flag_2nd_cddb ; set to 1 to indicate secondary
        56 00C0 C3 D0 1F6E 1664      movl    ucb$l_2p_cddb(r3),r6 ; pass the address of the secondary cddb
0000313C'EF 63 FA 1F73 1665      callg   (r3),show_cddb ; Display class driver data block
000024C9'EF 02 FB 1F7A 1666 30$:      calls   #2,show_iOq ; Display I/O request queue
00002AB1'EF 63 FA 1F81 1667      callg   (r3),show_vcb ; Display volume control block
        04 1F88 1668      ret
```



```

1F89 1670      .sbtll get_ucb, copy UCB to local storage
1F89 1671
1F89 1672      : This routine knows how to load enough of the UCB into local memory for
1F89 1673      : the operations performed above, but how to avoid trying to load more
1F89 1674      : UCB than there really is.
1F89 1675      :
1F89 1676      : Inputs:
1F89 1677      :
1F89 1678      :      r2      real UCB address
1F89 1679      :      r7      address of the place to copy it to
1F89 1680      :
1F89 1681      : Outputs:
1F89 1682      :
1F89 1683      :      r0      status of the copy operation
1F89 1684      :      r1      first longword of copied UCB
1F89 1685
1F89 1686
1F89 1687 get_ucb:
67 00CC 8F 00 6E 3C BB 1F89 1688      pushr    #^m<r2,r3,r4,r5>      ; save registers
                                movc5    #0,(sp),#0,#ucb_size,(r7) ; zero out the local ucb
                                popr     #^m<r2,r3,r4,r5>      ; restore registers
                                trymem   ucb$w_size(r2)        ; get size of this UCB
                                blbc     r0, 90$                ; exit now, if error occurred
                                movzwl   r1, r1                ; extend size to a longword
                                cmpl     r1, #ucb_size          ; is UCB bigger than the local space?
                                bleq     10$                     ; branch if not bigger
                                movzwl   #ucb_size, r1         ; else minimize the size
                                trymem   (r2), (r7), r1        ; copy UCB to local storage
                                rsb      10$, 90$              ; return to caller
                                05 1FC0 1698 90$:

```

```
1FC1 1700      .sbtbl show_ucb tables & action routines
1FC1 1701
1FC1 1702      .save
00001065 1703      .psect literals,exe,nowrt
1065 1704
1065 1705 ;
1065 1706 ; FAO control strings for locally generated UCB displays
1065 1707 ;
1065 1708
1065 1709 one_path:
0000106D'00000005' 1065 1710      .address 5, 10$
106D 1711 10$:      string ^\!40<!AC!AC!UW!>!17AC UCB address: !XL\
109B 1712
109B 1713 this_primary:
000010A3'00000008' 109B 1714      .address 8, 10$
10A3 1715 10$:      string ^\!40<!AC!AC!UW (!AC!AC!UW)!>!17AC UCB address: !XL\
10DD 1716
10DD 1717 this_secondary:
000010E5'00000008' 10DD 1718      .address 8, 10$
10E5 1719 10$:      string ^\!40<(!AC!AC!UW) !AC!AC!UW!>!17AC UCB address: !XL\
111F 1720
111F 1721 virtual_terminal:
00001127'00000007' 111F 1722      .address 7, 10$
1127 1723 10$:      string ^\!40<!AC!AC!UW ==> !AC!UW!>!17AC UCB address: !XL\
1160 1724
1160 1725 unknown:
6E 77 6F 6E 6B 6E 55 00' 1160 1726      .ascii /Unknown/
07 1160
1168 1727
1168 1728 ;
1168 1729 ; FAO control strings used by the action routines
1168 1730 ;
1168 1731
1168 1732 ucb_uic_cstr1:
1168 1733      string <[!60W,!60W]>
117B 1734
117B 1735 ucb_two_bytes:
117B 1736      string <!5XB/!2XB>
118C 1737
118C 1738 ucb_retry_fao:
118C 1739      string <!#UB/!UB>
119C 1740
119C 1741 ucb_test_retry_fao:
119C 1742      string <!UB>
11A7 1743
00001FC1 1744      .restore
1FC1 1745
1FC1 1746 ;
1FC1 1747 ; PRINT_COLUMNS tables for UCB display
1FC1 1748 ;
1FC1 1749
1FC1 1750 ucb_column_1:
1FC1 1751      column_list -
1FC1 1752          ucb$, 17, 8, 3, <- ; column 1 -- allocation
1FC1 1753          <<Owner UIC>,orb_owner,0,10,15>,- ; and other device status
1FC1 1754          <<PID>,l_pid,xl>,- ; Owner UIC
1FC1 1755          <<Alloc. lock Id>,ucb_lockid,0>,- ; Owner PID
1FC1 1755          ; Allocation lock ID
```

```
1FC1 1756 - ; Allocation class
1FC1 1757 <<Alloc. class>,ucb_allocclass,ucb_ddb>, -
1FC1 1758 <<Class/Type>,ucb_clstyp,0>, - ; Device class/type
1FC1 1759 <<Def. buf. size>,w_devbufsiz,uw>, - ; default buffer size
1FC1 1760 <<DEVDEPEND>,l_devdepend,xl>, - ; Device dependent first
1FC1 1761 <<DEVDEPEND2>,l_devdepend2,xl>, - ; sec.
1FC1 1762 <<FIPL/DIPL>,ucb_ipls,0>, - ; Fork / Device IPL
1FC1 1763 <<Charge PID>,ucb_cpids,0>, - ; UCB size charge PID
1FC1 1764 > ; *** end column 1
2071 1765
2071 1766 .save
0000057C 1767 .psect sdadata,noexe,wrt
057C 1768 ucb_ddb:
00000000 057C 1769 .long 0
00002071 1770 .restore
2071 1771
2071 1772 ucb_column_2:
2071 1773 column_list - ; column 2 -- device activity
2071 1774 ucb$, 18, 8, 3, < - ; data
2071 1775 <<Operation count>,l_opcnt,ul>, - ; operations completed
2071 1776 <<Error count>,w_errcnt,uw>, - ; errors recorded count
2071 1777 <<Reference count>,w_refc,uw>, - ; reference count
2071 1778 <<Online count>,ucb_onlcnt,0>, - ; online count
2071 1779 <<Retry cnt/max>,ucb_retry,0>, - ; error retry count/maximum
2071 1780 <<BOFF>,w_boff,xw>, - ; byte offset
2071 1781 <<Byte count>,w_bcmt,xw>, - ; byte count
2071 1782 <<SVAPTE>,l_svapte,xl>, - ; system virtual addr. PTE
2071 1783 <<SVPN>,ucb_svpn,0>, - ; system virtual page number
2071 1784 <<DEVSTS>,w_devsts,xw>, - ; Device dependent status
2071 1785 <<Master CSID>,ucb_mcsid,0>, - ; Master node's CSID
2071 1786 <<Int. due time>,ucb_duetim,0>, - ; Interrupt due time
2071 1787 <<RWAITCNT>,ucb_rwaitcnt,0>, - ; Reasons to wait count
2071 1788 > ; *** end column 2
2151 1789
2151 1790 ucb_column_3:
2151 1791 column_list - ; column 3 -- pointer addresses
2151 1792 ucb$, 15, 8, 0, < -
2151 1793 <<ORB address>,l_orb,xl>, - ; Object's rights block
2151 1794 <<DDB address>,l_ddb,xl>, - ; Device data block
2151 1795 <<DDT address>,l_ddt,xl>, - ; Driver dispatch table
2151 1796 <<VCB address>,ucb_vcb,0>, - ; Volume control block
2151 1797 <<CRB address>,l_crb,xl>, - ; Channel request block
2151 1798 <<LNM address>,ucb_lnm,0>, - ; MBX LNM pointer
2151 1799 <<AMB address>,l_amb,xl neq>, - ; Associated mailbox
2151 1800 <<PDT address>,ucb_pdt,0>, - ; Port descriptor table
2151 1801 <<CDDDB address>,ucb_cddb,0>, - ; Class driver data block
2151 1802 <<2P_CDDDB addr.>,ucb_2pcddb,0>, - ; Alternate CDDDB
2151 1803 <<2P_DDB address>,ucb_2pddb,0>, - ; Secondary path DDB
2151 1804 <<2P_UCB address>,ucb_altucb,0>, - ; Alternate UCB
2151 1805 - ; All of the following appear
2151 1806 - ; only when the UCB is busy
2151 1807 <<IRP address>,ucb_bsy,ucb$l_irp>, - ; I/O request packet
2151 1808 <<Fork PC>,ucb_bsy,ucb$l_fpc>, - ; Fork PC
2151 1809 <<Fork R3>,ucb_bsy,ucb$l_fr3>, - ; Fork R3
2151 1810 <<Fork R4>,ucb_bsy,ucb$l_fr4>, - ; Fork R4
2151 1811 <<I/O wait queue>,l_ioqft,q2>, - ; Pending I/O queue
2151 1812 > ; *** end column 3
```

```
2271 1813
2271 1814 : The following are all PRINT_COLUMNS action routines for the UCB
2271 1815 : display.
2271 1816 :
2271 1817 : Action Routine Inputs:
2271 1818 :
2271 1819 : R2 value from the COLUMN_LIST entry
2271 1820 : R5 size of value section for this item
2271 1821 : R7 address of a descriptor for a scratch string in
2271 1822 : which the FAO converted value is to be returned
2271 1823 : R11 base address of the local UCB copy
2271 1824 :
2271 1825 : Action Routine Outputs:
2271 1826 :
2271 1827 : R0 status
2271 1828 : lbs ==> use this entry
2271 1829 : lbc ==> skip this entry
2271 1830 :
2271 1831 : R1 - R5 scratch
2271 1832 : all other registers must be preserved
2271 1833 :
2271 1834 :*****
2271 1835 ucb_alloclass: ; if appropriate, return allocation class
2271 1836 : bbc #dev$u_fod, - ; branch if not a file oriented
2276 1836 : ucb$l_devchar(r11), ucb_act_nop ; device
2276 1837 : addl3 #ddb$l_allocls, (r2), r2 ; get allocation class address
227A 1838 ucb_act_ub: ; display allocation class
227A 1839 : do_column_entry ub, jmp
2283 1840 :
2283 1841 :*****
2283 1842 ucb_altucb:
2283 1843 : bbc #dev$u_2p, ucb$l_devchar2(r11), - ; branch if device is not
2288 1844 : ucb_act_nop ; dual pathed
2288 1845 : movl ucb$l_dp_altucb(r11), r2 ; alternate UCB address
228D 1846 : tstl (r2) ; is there something there?
228F 1847 : beql ucb_act_nop ; branch if nothing there
2291 1848 : make_symbol - ; else,
2291 1849 : 2P UCB, (r2) ; make a symbol and
22A6 1850 : brw ucb_act_xl ; display it
22A9 1851 :
22A9 1852 :*****
22A9 1853 ucb_bsy:
22A9 1854 : bbc #ucb$u_bsy, ucb$l_sts(r11), - ; exit doing nothing if the
22AE 1855 : ucb_act_nop ; UCB is not busy
22AE 1856 : addl r11, r2 ; else locate cell to return
22B1 1857 ucb_act_xl_neq:
22B1 1858 : do_column_entry xl_neq, jmp ; display that entry
22BB 1859 :
22BB 1860 :*****
22BB 1861 ucb_clstyp: ; return device class / type
22BB 1862 : movzbl ucb$b_devclass(r11), r2 ; return device class
22BF 1863 : movzbl ucb$b_devtype(r11), r3 ; and device type
22C3 1864 : brb ucb_ret_2xbytes ; go join common code
22C5 1865 :
22C5 1866 :*****
22C5 1867 ucb_cpuid: ; if appropriate, return PID charged for UCB creation
22C5 1868 : bitl #<dev$m_mbx ! dev$m_net>, - ; is this a mailbox or a
22CD 1869 : ucb$l_devchar(r11) ; network device
```

```

      52  20 06 13 22CD 1870      beql  ucb_act_nop      ; if not, assume no PID charged
      AB  DE 22CF 1871      moval  ucb$l_cpuid(r11), r2    ; else, return charged PID
      5B  11 22D3 1872      brb    ucb_act_xl           ; using common code
      22D5 1873
      22D5 1874 ucb_act_nop:
      50  D4 22D5 1875      clrl   r0                    ; make this call a nop
      05  22D7 1876      rsb     ; return
      22D8 1877
      22D8 1878 ;*****
      FB 64 AB 00 E1 22D8 1879 ucb_duetim: ; if appropriate, return interrupt due time
      22D8 1880      bbc     #ucb$sv_tim, - ; branch if time-out not
      22DD 1881      ucb$l_sts(r11), ucb_act_nop ; expected
      52  6C AB DE 22DD 1882      moval  ucb$l_duetim(r11), r2 ; else return due time
      4D  11 22E1 1883      brb    ucb_act_xl           ; join common code
      22E3 1884
      22E3 1885 ;*****
      52  0B AB 9A 22E3 1886 ucb_ipls: ; return fork / device IPL
      53  5E AB 9A 22E7 1888      movzbl ucb$b_fipl(r11), r2 ; return fork IPL
      22EB 1889      movzbl ucb$b_dipl(r11), r3 ; and device IPL
      22EB 1890 ucb_ret_2xbytes:
      22EB 1891      $fao_s - ; two values as requested
      22EB 1892      ctrstr = ucb_two_bytes, -
      22EB 1893      outbuf = (r7), -
      22EB 1894      outlen = (r7), -
      22EB 1895      p1 = r2, -
      22EB 1896      p2 = r3
      05  2300 1896      rsb     ; return
      2301 1897
      2301 1898 ;*****
      40 AB A0 8F 91 2301 1899 ucb_lnm:
      2306 1901      cmpb     #dc$ mailbox, - ; is this a mailbox?
      2306 1902      bneq    ucb_act_nop ; branch if not a mailbox
      52  74 AB DE 2308 1903      moval  ucb$l_logadr(r11), r2 ; get logical name pointer
      62  D5 230C 1904      tstl   (r2) ; is something there?
      C5  13 230E 1905      beql    ucb_act_nop ; branch if nothing there
      2310 1906      make_symbol - ; else,
      2310 1907      LNM, (r2) ; make a symbol and
      09  11 2325 1908      brb     ucb_act_xl ; display it
      2327 1909
      2327 1910 ;*****
      A9 3C AB 00 E1 2327 1911 ucb_lockid: ; if sensible, return allocation lock id
      232C 1912      bbc     #dev$sv_clu, - ; branch if not a cluster
      52  20 AB DE 232C 1913      ucb$l_devchar2(r11), ucb_act_nop ; accessible device
      2330 1914      moval  ucb$l_lockid(r11), r2 ; else return lock id
      2330 1915 ucb_act_xl:
      2330 1916      do_column_entry xl, jmp
      2339 1917
      2339 1918 ;*****
      40 AB A1 8F 91 2339 1919 ucb_mcsid:
      233E 1920      cmpb     #dc$ journal, - ; is this a journal device?
      233E 1921      bneq    ucb_act_nop ; branch if not a journal dev.
      52  0084 CB DE 2340 1923      moval  ucb$l_jnl_mcsid(r11), r2 ; else, return master CSID
      E9  11 2345 1924      brb     ucb_act_xl ; using common code
      2347 1925
      2347 1926 ;*****
```

```
2347 1927 ucb_onlcnt:
40 AB 01 91 2347 1928      cmpb    #dc$b_devclass(r11) ; is this a disk device?
52 00AE CB 12 2348 1929      bneq     ucb_act_nop_a ; branch if not a disk
      FF25 31 234D 1930      movab    ucb$b_onlcnt(r11), r2 ; else get online count addr.
      2352 1931      brw      ucb_act_ub ; and display it
      2355 1932
      2355 1933 ;*****
      2355 1934 orb_owner: ; attempt to format owner UIC
51 52 7E D4 2355 1935      clr     -(sp) ; storage for the UIC from ORB
      5E D0 2357 1936      movl     sp, r2 ; save address for later
      1C AB D0 235A 1937      movl     ucb$l_orb(r11), r1 ; get real ORB address
      OF 13 235E 1938      beql     10$ ; display [0,0] if no ORB
      03 50 E9 2360 1939      getmem   orb$l_owner(r1) ; get the owner UIC
      62 51 D0 2369 1940      blbc     r0, 10$ ; display [0,0] if unaccessible
      236C 1941      movl     r1, (r2) ; save for $FA0 below
      236F 1942      ASSUME    ORB$l_OWNER EQ 0
      236F 1943 10$:      $fao_s - ; convert UIC to octal
      236F 1944      ctrstr = ucb_uic_cstr1, -
      236F 1945      outbuf = (r7), -
      236F 1946      outlen = (r7), -
      236F 1947      p1 = orb$b_uicgroup(r2), -
      236F 1948      p2 = orb$b_uicmember(r2)
      8E D5 2385 1949      tstl     (sp)+ ; clean the stack
      05 2387 1950      rsb ; return
      2388 1951
      2388 1952 ;*****
      2388 1953 ucb_pdt:
53 0084 CB D0 2388 1954      movl     ucb$l_pdt(r11), r3 ; get possible PDT address
      2E 13 238D 1955      beql     ucb_act_nop_a ; branch if none
51 0560 8F B1 238F 1956      getmem   ucb$b_type(r3) ; get type and sub-type of PDT
      2399 1957      cmpw     #<dyn$c_scs_pdt>8 - ; is thing pointed to really
      239E 1958      + dyn$c_scs>, r1 ; a PDT?
52 0084 1D 12 239E 1959      bneq     ucb_act_nop_a ; branch if not really a PDT
      CB DE 23A0 1960      moval     ucb$l_pdt(r11), r2 ; get address of PDT pointer
      23A5 1961      make_symbol -
      23A5 1962      PDT, (r2) ; make a symbol and
      FF73 31 23BA 1963      brw      ucb_act_xl ; display it
      23BD 1964
      23BD 1965
      23BD 1966 ucb_act_nop_a:
      50 D4 23BD 1967      clr     r0
      05 23BF 1968      rsb
      23C0 1969
      23C0 1970 ;*****
      23C0 1971 ucb_cddb:
3C AB 05 E1 23C0 1972      bbc     #dev$b_mscp, ucb$l_devchar2(r11), -
52 00BC CB DE 23C4 1973      ucb_act_nop_a ; branch if device is not mscp serve
      23C5 1974      moval     ucb$l_cddb(r11), r2 ; get address of Cddb pointer
      23CA 1975      make_symbol -
      23CA 1976      Cddb, (r2) ; make a symbol and
      FF4E 31 23DF 1977      brw      ucb_act_xl ; display it
      23E2 1978
      23E2 1979 ;*****
      23E2 1980 ucb_2pcddb:
3C AB 05 E1 23E2 1981      bbc     #dev$b_mscp, ucb$l_devchar2(r11), -
52 00C0 CB DE 23E6 1982      ucb_act_nop_a ; branch if device is not mscp serve
      23E7 1983      moval     ucb$l_2p_cddb(r11), r2 ; alternate Cddb address
```

```

        62 D5 23EC 1984      tstl      (r2)                ; is there a secondary cddb
        CD 13 23EE 1985      beql      ucb_act_nop_a        ; branch if not
                23F0 1986      make_symbol -                ;
        FF28 31 23F0 1987      2P CDDb, (r2)                ; make a symbol and
                2405 1988      brw      ucb_act_xl          ; display it
                2408 1989
                2408 1990 ;*****
                2408 1991 ucb_retry:
        0081 CB 95 2408 1992      tstb      ucb$b_ertmax(r11)    ; is there a retry max?
                AF 13 240C 1993      beql      ucb_act_nop_a    ; quit now, if no retry max
                7E D4 240E 1994      clrl      -(sp)           ; make a little room on stack
        52 5E D0 2410 1995      movl      sp, r2              ; save its address
                2413 1996      $fao_s -
                2413 1997      ctrstr = ucb_test_retry_fao, - ; determine size of
                2413 1998      outbuf = (r7), -              ; retry max
                2413 1999      outlen = (r2), -
                2413 2000      p1 = ucb$b_ertmax(r11)
        55 6E D6 2428 2001      incl      (sp)                ; add one to retry max size
                8E C2 242A 2002      subl      (sp)+, r5       ; reduce retry cnt. size by that
                242D 2003      $fao_s -
                242D 2004      ctrstr = ucb_retry_fao, -      ; now produce the whole value
                242D 2005      outbuf = (r7), -
                242D 2006      outlen = (r7), -
                242D 2007      p1 = r5, -
                242D 2008      p2 = ucb$b_ertcnt(r11), -
                242D 2009      p3 = ucb$b_ertmax(r11)
                05 2448 2010      rsb                          ; then return
                2449 2011
                2449 2012 ;*****
        3C AB 05 E1 2449 2013 ucb_rwaitcnt:
                78 244D 2014      bbc      #dev$u_mscp,ucb$l_devchar2(r11),- ; branch if device is not mscp serve
        52 56 AB DE 244E 2015      moval      ucb_act_nop_b        ; get address of wait count
                2452 2016      make_symbol - ucb$w_rwaitcnt(r11),r2
                2452 2017      RWAITCNT,(r2)                ; make a symbol and
                2467 2019 ucb_act_xw:
                2467 2020      do_column_entry xw,jmp
                2470 2021
                2470 2022 ;*****
        40 AB A0 8F 91 2470 2023 ucb_svpn:
                2475 2024      cmpb      #dc$ mailbox, -      ; is this a mailbox? (they
                2475 2025      ucb$b_devclass(r11)           ; don't have SVPN's)
                52 4F 13 2475 2026      beql      ucb_act_nop_b    ; branch if mailbox
                74 AB DE 2477 2027      moval      ucb$l_svpn(r11), r2 ; get SVPN address
                FE33 31 247B 2028      brw      ucb_act_xl_neq    ; display it if non-zero
                247E 2029
                247E 2030 ;*****
        38 AB 00280000 8F D3 247E 2031 ucb_vcb:
                2486 2032      bitl      #<dev$m_mnt ! dev$m_dmt>, - ; is the device mounted?
                2486 2033      ucb$l_devchar(r11)
                52 3E 13 2486 2034      beql      ucb_act_nop_b    ; branch if not mounted
                34 AB DE 2488 2035      moval      ucb$l_vcb(r11), r2
                248C 2036      make_symbol -
                248C 2037      VCB, (r2)
                FE8C 31 24A1 2038      brw      ucb_act_xl          ; make a symbol and
                24A4 2039                                     ; and display it
                24A4 2040 ;*****
```

```

1D 3C AB 04 E1 24A4 2041 ucb_2pddb:
                24A4 2042      bbc      #dev$u_2p, ucb$l_devchar2(r11), - ; branch if device is not
                24A9 2043      ucb_act_nop_b      ; dual pathed
52 00A0 CB DE 24A9 2044      moval    ucb$l_dp_ddb(r11), r2      ; secondary DDB address
                24AE 2045      make_symbol -
                24AE 2046      2P DDB, (r2)      ; make a symbol and
                24C3 2047      brw      ucb_act_xl_neq      ; display it
                24C6 2048
                24C6 2049 ucb_act_nop_b:
50          04 24C6 2050      clr     r0
          05 24C8 2051      rsb
          24C9 2052

```



```
24C9 2054 .sbttl show_ioq, Display I/O queue for device
24C9 2055 :---
24C9 2056 :
24C9 2057 show_ioq
24C9 2058 :
24C9 2059 Display the IRPs and/or CDRP's (if mscp served) in the I/O queues
24C9 2060 associated with a specified device.
24C9 2061 :
24C9 2062 Inputs:
24C9 2063 :
24C9 2064 4(ap) = Address of UCB in local storage
24C9 2065 8(ap) = Actual address of UCB
24C9 2066 :
24C9 2067 :---
24C9 2068 .enabl lsb
24C9 2069 :
24C9 2070 show_ioq:
24C9 2071 .word ^m<r2,r3,r4,r5,r6,r7,r8>
24CB 2072 :
24CB 2073 movl 4(ap),r2 ; address of UCB
24CF 2074 bbc #dev$V_mscp,ucb$l_devchar2(r2),5$
24D4 2075 : ; only 1 queue if not mscp served
24D4 2076 movab cddb,r7 ; address of Class Driver Data Block
24DB 2077 getmem @ucb$l_cddb(r2),(r7),#cddb$c_length ; read CDDB
24EE 2078 blbc r0,8$ ; branch if cannot read entire CDDB
54 00BC C2 00 C1 24F1 2079 addl3 #cddb$l_cdrpqfl,ucb$l_cddb(r2),r4 ; Get real address of cdrp q
54 54 67 D1 24F7 2080 cmpl cddb$l_cdrpqfl(r7),r4 ; Empty CDRP queue?
54 54 45 12 24FA 2081 bneq 10$ ; branch if not empty
54 00BC C2 3C C1 24FC 2082 4$: addl3 #cddb$l_rstrtqfl,ucb$l_cddb(r2),r4 ; Get real address of restart qu
54 54 3C A7 D1 2502 2083 cmpl cddb$l_rstrtqfl(r7),r4 ; Empty restart queue
54 08 AC 0000004C 50 12 2506 2084 bneq 30$ ; branch if not empty
54 54 4C A2 D1 2508 2085 5$: addl3 #ucb$l_ioqfl,8(ap),r4 ; Get real address of queue header
1F 64 A2 08 E0 2511 2086 cmpl ucb$l_ioqfl(r2),r4 ; Empty i/o queue?
00000577'EF 95 2515 2087 bneq 7$ ; Branch if not
1A 12 2517 2088 bbs #ucb$V_bsy,ucb$W_sts(r2),7$ ; Branch if have IRP
251C 2089 tstb queue_notempty ; if 0 all queues are empty
2522 2090 bneq 8$ ; if 1 then at least 1 queue was not empty
2524 2091 skip 1
252D 2092 print 0,<!-- I/O request queue is empty -->
253A 2093 ret
253B 2094 :
0033 31 253B 2095 7$: brw 50$ ; process io request queue
0064 31 253E 2096 8$: brw 90$ ; clear queue flag and return
2541 2097 :
2541 2098 : Queue - Class Driver Request Packet Queue (CDRP)
2541 2099 :
53 67 D0 2541 2100 10$: movl cddb$l_cdrpqfl(r7),r3 ; Get address of first entry in queue
56 01 D0 2544 2101 : movl #1,r6 ; Set state to current
58 08 AC D0 2547 2102 : movl 8(ap),r8 ; pass actual address of ucb in r8
53 02D5 30 2548 2103 20$: bsbw print_cdrp ; display the contents of the cdrp
54 65 D0 254E 2104 : movl cdrp$l_fqfl(r5),r3 ; advance to next entry in queue
54 53 D1 2551 2105 : cmpl r3,r4 ; check to see if another entry exists
A6 13 2554 2106 : beql 4$ ; if points back to beginning no more
F3 11 2556 2107 : brb 20$ ; process this entry in queue
2558 2108 :
2558 2109 : Queue - Restarted Class Driver Request Packet Queue (RSTRTQ)
2558 2110 :
```

```
53 3C A7 D0 2558 2111 30$: movl cddb$l_rstrtqfl(r7),r3 ; Get first entry in queue
56 56 02 D0 255C 2112      movl #2,r6 ; State is restart
58 08 AC D0 255F 2113      movl 8(ap),r8 ; pass actual address of ucb in r8
02BD 30 2563 2114 40$: bsbw print_cdrp ; Call routine to display this cdrp
53 65 D0 2566 2115      movl cdrp$l_fqfl(r5),r3 ; Advance to next entry in queue
54 53 D1 2569 2116      cmpl r3,r4 ; Check to see if no more entries in queue
F5 12 256C 2117      bneq 40$ ; if eql branch to check next queue
FF97 31 256E 2118      brw 5$ ; otherwise still more entries here to proce
2571 2119 :
2571 2120 :
2571 2121 :
Queue - Standard IO Request Packet Queue (IRP)
00000577'EF 95 2571 2122 50$: tstb queue_notempty ; Check to see if anyone set this flag
OA 12 2577 2123      bneq 55$ ; if 1 then yes so don't bother with it
03E6 30 2579 2124      bsbw queue_title ; print header for page (IO Request Queue)
00000577'EF 01 90 257C 2125      movb #1,queue_notempty ; set flag to indicate queue was not empty
OA 64 A2 08 E1 2583 2126 55$: bbc #ucb$b_sy,ucb$b_w_sts(r2),60$ ; Branch if not busy
53 58 A2 D0 2588 2127      movl ucb$l_irp(r2),r3 ; Address of current IRP
56 01 D0 258C 2128      movl #1,r6 ; Indicate current IRP
043E 30 258F 2129      bsbw print_irp ; Print line for current IRP
2592 2130
53 4C A2 D0 2592 2131 60$: movl ucb$l_ioqfl(r2),r3 ; Get address of first IRP in queue
56 D4 2596 2132      clrl r6 ; Indicate not current IRP
2598 2133
54 53 D1 2598 2134 70$: cmpl r3,r4 ; end of queue?
08 13 259B 2135      beql 90$ ; Branch if so
0430 30 259D 2136      bsbw print_irp ; print IRP line
53 65 D0 25A0 2137      movl irp$l_ioqfl(r5),r3 ; Skip to next IRP in queue
F3 11 25A3 2138      brb 70$
25A5 2139
00000577'EF 94 25A5 2140 90$: clrb queue_notempty ; clear flag before we are called again
04 25AB 2141      status success
25B2 2142      ret
25B3 2143      .dsabl lsb
```

```

25B3 2145 .sbttl show_acpq, display acp queue
25B3 2146 :---
25B3 2147 :
25B3 2148 : show_acpq
25B3 2149 :
25B3 2150 : Display the IRP queue associated with the ACP
25B3 2151 : on the current volume.
25B3 2152 :
25B3 2153 : Inputs:
25B3 2154 :
25B3 2155 : ap = address of VCB in local storage
25B3 2156 :
25B3 2157 :---
25B3 2158 : .enabl lsb
25B3 2159 :
25B3 2160 show_acpq:
25B3 2161 .word ^m<r2,r3,r4,r5,r6>
25B5 2162
25B5 2163 10 AC D5 25B5 2163 tstl vcb$l_aqb(ap) ; Is there any AQB?
03 12 25B8 2164 bneq 10$ ; Branch if so
0188 31 25BA 2165 90$: brw 95$ ; Exit
25B0 2166
52 0000041D'EF 9E 25B0 2167 10$: movab aqb,r2
25C4 2168 getmem avcb$l_aqb(ap),(r2),#aqb$c_length ; Read entire AQB
E5 50 E9 25D2 2169 blbc r0,90$
25D5 2170 ensure 11
10 AC DD 25ED 2171 pushl vcb$l_aqb(ap)
25F0 2172 skip 1
25F9 2173 print 1,<!_!_ --- ACP Queue Block (AQB) !XL --->
2606 2174 skip 1
0C A2 D5 260F 2175 tstl aqb$l_acppid(r2) ; Is the XQP servicing this queue?
53 13 2612 2176 beql 20$ ; Branch if XQP
2614 2177 getmem asch$gl_pcbvec,r3 ; Get address of PCB vector
4D 50 E9 2624 2178 blbc r0,30$
51 0C A2 32 2627 2179 cvtwt aqb$l_acppid(r2),r1 ; Extract process index
51 6341 DE 262B 2180 moval (r3)[r1],r1 ; Point to PCB address entry
262F 2181 getmem (r1) ; Read PCB address
39 50 E9 2638 2182 blbc r0,30$
53 00000000'EF 9E 2638 2183 movab buffer,r3
2642 2184 getmem pcb$[name(r1),(r3),#16 ; Read 16-byte process name
21 50 E9 2650 2185 blbc r0,30$
0C A2 DD 2653 2186 pushl aqb$l_acppid(r2) ; Process PID
53 DD 2656 2187 pushl r3 ; Address of ASCII string
2658 2188 print 1,<ACP requests are serviced by process !AC whose PID is !XL>
0D 11 2665 2189 brb 30$
2667 2190
2667 2191 20$: print 0,<ACP requests are serviced by the eXtended Qio Processor (XQP)>
2674 2192
2674 2193 30$: skip 1
267D 2194 alloc 80 ; 80 byte string buffer
7E 14 A2 9A 268C 2195 movzbl aqb$b_status(r2),-(sp) ; ACP status
E504 CF 9F 2690 2196 pushab acp_status ; Bit definition table
00000000'EF 02 FB 2694 2197 calls #2,translate_bits ; Translate bits into names
SE DD 269B 2198 pushl sp ; Address of string descriptor
14 A2 DD 269D 2199 pushl aqb$b_status(r2) ; ACP status
26A0 2200 print 2,<Status: !XB !AS>
26AD 2201 skip 1

```

```

26B6 2202      print_columns -
26B6 2203      (r2), vcb$aqb(ap), -
26B6 2204      aqb_column_1, aqb_column_2, aqb_column_3
26D4 2205
26D4 2206      skip      1
54   10 53    62    D0 26DD 2207      movl      aqb$aqpql(r2), r3          ; Get address of first IRP
AC    00    C1 26E0 2208      addl3     #aqb$aqpql, vcb$aqb(ap), r4        ; Get real address of queuehead
54    53    D1 26E5 2209      cmpl      r3, r4              ; Empty ACP queue?
OE    OE    D1 26E8 2210      bneq       70$             ; Branch if not
26EA 2211      print      0, <!--*** ACP request queue is empty ***>
04    04    D1 26F7 2212      ret
26F8 2213
26F8 2214 70$:      ensure     8
2710 2215      print      0, <!--!-!-!- ACP request queue>
271D 2216      print      0, <!--!-!-!- ----->
272A 2217      skip      1
026C 30 2733 2218      bsbw      irp_heading           ; Print heading line
56    D4 2736 2219      clrl      r6               ; Indicate not current IRP
2738 2220
54    53    D1 2738 2221 80$:      cmpl      r3, r4              ; End of queue?
08    13 273B 2222      beql       95$             ; Branch if so
0290 30 273D 2223      bsbw      print_irp            ; Print IRP line
53    65    D0 2740 2224      movl      irp$aioqfl(r5), r3         ; skip to next IRP
F3    F3    D0 2743 2225      brb        80$
2745 2226
2745 2227 95$:      status     success
04    04    D1 274C 2228      ret
274D 2229      .dsabl     lsb
274D 2230      .sbtll     volume control block tables & action routines
274D 2231
274D 2232 : The following are all PRINT_COLUMNS action routines for the show_vcb
274D 2233 : block displays.
274D 2234 :
274D 2235 : Action Routine Inputs:
274D 2236 :
274D 2237 : R2 value from the COLUMN_LIST entry
274D 2238 : R5 size of value section for this item
274D 2239 : R7 address of a descriptor for a scratch string in
274D 2240 : which the FAO converted value is to be returned
274D 2241 : R11 base address of the local UCB copy
274D 2242 :
274D 2243 : Action Routine Outputs:
274D 2244 :
274D 2245 : R0 status
274D 2246 : lbc ==> use this entry
274D 2247 : lbc ==> skip this entry
274D 2248 : R1 - R5 scratch
274D 2249 : all other registers must be preserved
274D 2250 :
274D 2251 :
274D 2252 : PRINT_COLUMNS tables for AQB display
274D 2253 :
274D 2254 :
274D 2255 :
274D 2256 aqb_column_1:
274D 2257 column_list -
274D 2258 aqb$, 16, 8, 4, <-

```

```

274D 2259      <<Mount count>,b_mntcnt,ub>, -
274D 2260      >
276D 2261
276D 2262 aqb_column_2:
276D 2263      column_list -
276D 2264      aqb$, 16, 8, 4, < -
276D 2265      <<ACP type>,aqb_type,0,14,10>, -
276D 2266      <<ACP class>,aqb_class,0>, -
276D 2267      >
279D 2268
279D 2269 aqb_column_3:
279D 2270      column_list -
279D 2271      aqb$, 16, 8, 0, < -
279D 2272      <<Linkage>,[_link,xl_neg>, -
279D 2273      <<Request queue>,[_acpqfl,q2>, -
279D 2274      >
27CD 2275
27CD 2276 ;*****
27CD 2277 aqb_type:
27CD 2278      movzbl aqb$b_acptype(r11), r2      ; get ACP type
27D1 2279      movab aqb_acptype, r3          ; get translate table
27D6 2280      jsb g^ttranslate_address      ; translate ACP class
27DC 2281      beql 90$                      ; branch if translate failed
27DE 2282      movl r0, r2                  ; setup translated string
27E1 2283      do_column_entry ac, jmp        ; display translation
27EA 2284
27EA 2285 90$: movab aqb$b_acptype(r11), r2      ; else, get type address
27EE 2286      do_column_entry ub, jmp        ; just display the value
27F7 2287
27F7 2288 ;*****
27F7 2289 aqb_class:
27F7 2290      movzbl aqb$b_class(r11), r2        ; get ACP class
27FB 2291      beql 90$                          ; branch if none
27FD 2292      movab ddb_acpclass, r3              ; get translate table
2802 2293      jsb g^ttranslate_address      ; translate ACP class
2808 2294      beql 90$                      ; branch if translate failed
280A 2295      movl r0, r2                  ; setup translated string
280D 2296      do_column_entry ac, jmp        ; display translation
2816 2297
2816 2298 90$: movab ddb$b_acpclass(r11), r2      ; else, get class address
281A 2299      do_column_entry ub, jmp        ; just display the value

```

```
2823 2301 .sbtll print_cdrp, print a single CDRP block
2823 2302 :---
2823 2303
2823 2304 .enabl lsb
2823 2305 :
2823 2306 Subroutine to print information for a single CDRP block
2823 2307 :
2823 2308 Inputs:
2823 2309 :
2823 2310 r3 = Dump address of CDRP block
2823 2311 r6 = 2, if restarted CDRP, 1 if current CDRP
2823 2312 r8 = Actual address of UCB
2823 2313 :
2823 2314 Outputs:
2823 2315 :
2823 2316 r5 = Address of CDRP in local storage
2823 2317 :
2823 2318 :---
2823 2319
2823 2320 print_cdrp:
2823 2321 ensure 3
2823 2322 pushl r6 : save r6
2823 2323 addl3 #cdrp$l_ioqfl,r3,r6 : get start of cdrp at most negative offset
2823 2324 movab cdrp,r5 : get address of local cdrp
2823 2325 getmem (r6),(r5),#cdrp_length : read entire CDRP
2823 2326 popl r6 : restore r6
2823 2327 blbs r0,5$ : check status
2823 2328 brw 90$ : return
2823 2329 5$: subl2 #cdrp$l_ioqfl,r5 : actual start of CDRP
2823 2330 cmpl r8,cdrp$l_ucb(r5) : check to see if this request is from this
2823 2331 beql 10$ : if equal yes so process it
2823 2332 brw 90$ : return
2823 2333 10$: tstb queue_notempty : Check to see if anyone set this flag
2823 2334 bneq 15$ : If 1 then yes so don't bother with it
2823 2335 bsbw queue_title : Otherwise display the header for page
2823 2336 movb #1,queue_notempty : set flag to say this queue was not empty
2823 2337 15$: pushl cdrp$w_sfs(r5) : request status
2823 2338 pushl cdrp$l_iosb(r5) : address of IOSB
2823 2339 pushl cdrp$l_ast(r5) : address of AST routine
2823 2340 pushl cdrp$b_efn(r5) : Event flag number
2823 2341 pushl cdrp$l_wind(r5) : Address of WCB
2823 2342 pushl cdrp$w_func(r5) : Function code
2823 2343 pushl cdrp$w_chan(r5) : Channel number
2823 2344 extzv #irp$w_mode,#irp$w_mode,cdrp$b_rmod(r5),r0
2823 2345 pushl #^a'KESU' : Possible user modes
2823 2346 pushab (sp)[r0] : Address of string
2823 2347 pushl #1 : Length of string
2823 2348 pushl cdrp$l_pid(r5) : Process identification
2823 2349 pushl r3 : Address of CDRP
2823 2350 pushl #^a'C' : String containing space
2823 2351 pushl sp : Address of string
2823 2352 pushl #1 : Length of string
2823 2353 cmpl #1,r6 : check if current CDRP
2823 2354 beql 20$ : branch if not
2823 2355 movl #^a'R',8(sp) : Flag current CDRP being done
2823 2356 20$: print 15,< !AD!+ !XL !XL !AD!+ !XW !XW !XL !20B !XL !XL !XW>
2823 2357
```

56	53	FFFFFFA0	8F	DD	283B	2322			
	55	00000289	'EF	9E	283D	2323			
					2845	2324			
					284C	2325			
					285D	2326			
					2860	2327			
					2863	2328			
					2866	2329	5\$:		
					286D	2330			
					2871	2331			
					2873	2332			
					2876	2333	10\$:		
					287C	2334			
					287E	2335			
					2881	2336			
					2888	2337	15\$:		
					288B	2338			
					288E	2339			
					2891	2340			
					2894	2341			
					2897	2342			
					289A	2343			
					289D	2344			
					28A3	2345			
					28A9	2346			
					28AC	2347			
					28AE	2348			
					28B1	2349			
					28B3	2350			
					28B9	2351			
					28BB	2352			
					28BD	2353			
					28C0	2354			
					28C2	2355			
					28CA	2356	20\$:		
					28D7	2357			

56	53	FFFFFFA0	8F	DD	283B	2322			
	55	00000289	'EF	9E	283D	2323			
					2845	2324			
					284C	2325			
					285D	2326			
					2860	2327			
					2863	2328			
					2866	2329	5\$:		
					286D	2330			
					2871	2331			
					2873	2332			
					2876	2333	10\$:		
					287C	2334			
					287E	2335			
					2881	2336			
					2888	2337	15\$:		
					288B	2338			
					288E	2339			
					2891	2340			
					2894	2341			
					2897	2342			
					289A	2343			
					289D	2344			
					28A3	2345			
					28A9	2346			
					28AC	2347			
					28AE	2348			
					28B1	2349			
					28B3	2350			
					28B9	2351			
					28BB	2352			
					28BD	2353			
					28C0	2354			
					28C2	2355			
					28CA	2356	20\$:		
					28D7	2357			

```
28D7 2358 ; save a few registers now. Then we will allocate stack space for two output
28D7 2359 ; buffers. Translate the class driver's flags field, the status field of the
28D7 2360 ; cdrp, and the function code for the request. Then display.
28D7 2361 ;
7E 52 7D 28D7 2362 movq r2, -(sp) ; save some registers
28DA 2363 alloc 80,r2 ; 80 byte output buffer for request status
28EC 2364 alloc 80,r3 ; another buffer of 80 bytes
7E 40 A5 D0 28FE 2365 movl cdrp$l_dutuflags(r5),-(sp) ; cdrp flags
E0D2 CF 9F 2902 2366 pushab cdrp_dutuflags ; bit definition table
00000000'EF 02 FB 2906 2367 calls #2,translate_bits ; translate bits to names
5E DD 290D 2368 pushl sp ; push the address of descriptor
04 A2 DD 290F 2369 pushl 4(r2) ; push descriptor for request status
7E CA A5 3C 2912 2370 pushl (r2) ; push size of this buffer
E0F4 CF 9F 2914 2371 movzwl cdrp$w_sts(r5),-(sp) ; request status
00000000'EF 02 FB 2918 2372 pushab request_status ; bit definition table
5E DD 2923 2373 calls #2,translate_bits ; translate bits to names
00000E21'EF 9F 2925 2374 pushl sp ; address of string descriptor
52 C0 A5 06 00 EF 2928 2375 pushab null_ascii ; assume function will not translate
2931 2376 extzv #io$v_fcode, #io$s_fcode, -
2931 2377 cdrp$w_func(r5), r2 ; get function code
53 E153 CF 9E 2931 2378 movab io_function, r3 ; get translation table
00000000'GF 16 2936 2379 jsb g^translate_address ; translate function to text
03 13 293C 2380 beql 33$ ; branch if translate failed
6E 50 D0 293E 2381 movl r0, (sp) ; setup translated function
2941 2382 33$: print 3,<_!AC !AS!+!+ !AS> ; print translated information
294E 2383 skip 1 ; advance
5E 000000B8 8F C0 2957 2384 addl #184,sp ; deallocate translate buffers
52 8E 7D 295E 2385 movq (sp)+, r2 ; restore saved registers
2961 2386
05 2961 2387 90$: rsb
```

[illegible]

[illegible]

PC	Op	Op2	Op3	Op4	Op5	Op6	Op7	Op8	Op9	Op10	Op11	Op12	Op13	Op14	Op15	Op16	Op17	Op18	Op19	Op20	Op21	Op22	Op23	Op24	Op25	Op26	Op27	Op28	Op29	Op30	Op31	Op32	Op33	Op34	Op35	Op36	Op37	Op38	Op39	Op40	Op41	Op42	Op43	Op44	Op45	Op46	Op47	Op48	Op49	Op50	Op51	Op52	Op53	Op54	Op55	Op56	Op57	Op58	Op59	Op60	Op61	Op62	Op63	Op64	Op65	Op66	Op67	Op68	Op69	Op70	Op71	Op72	Op73	Op74	Op75	Op76	Op77	Op78	Op79	Op80	Op81	Op82	Op83	Op84	Op85	Op86	Op87	Op88	Op89	Op90	Op91	Op92	Op93	Op94	Op95	Op96	Op97	Op98	Op99	Op100	Op101	Op102	Op103	Op104	Op105	Op106	Op107	Op108	Op109	Op110	Op111	Op112	Op113	Op114	Op115	Op116	Op117	Op118	Op119	Op120	Op121	Op122	Op123	Op124	Op125	Op126	Op127	Op128	Op129	Op130	Op131	Op132	Op133	Op134	Op135	Op136	Op137	Op138	Op139	Op140	Op141	Op142	Op143	Op144	Op145	Op146	Op147	Op148	Op149	Op150	Op151	Op152	Op153	Op154	Op155	Op156	Op157	Op158	Op159	Op160	Op161	Op162	Op163	Op164	Op165	Op166	Op167	Op168	Op169	Op170	Op171	Op172	Op173	Op174	Op175	Op176	Op177	Op178	Op179	Op180	Op181	Op182	Op183	Op184	Op185	Op186	Op187	Op188	Op189	Op190	Op191	Op192	Op193	Op194	Op195	Op196	Op197	Op198	Op199	Op200	Op201	Op202	Op203	Op204	Op205	Op206	Op207	Op208	Op209	Op210	Op211	Op212	Op213	Op214	Op215	Op216	Op217	Op218	Op219	Op220	Op221	Op222	Op223	Op224	Op225	Op226	Op227	Op228	Op229	Op230	Op231	Op232	Op233	Op234	Op235	Op236	Op237	Op238	Op239	Op240	Op241	Op242	Op243	Op244	Op245	Op246	Op247	Op248	Op249	Op250	Op251	Op252	Op253	Op254	Op255	Op256	Op257	Op258	Op259	Op260	Op261	Op262	Op263	Op264	Op265	Op266	Op267	Op268	Op269	Op270	Op271	Op272	Op273	Op274	Op275	Op276	Op277	Op278	Op279	Op280	Op281	Op282	Op283	Op284	Op285	Op286	Op287	Op288	Op289	Op290	Op291	Op292	Op293	Op294	Op295	Op296	Op297	Op298	Op299	Op300	Op301	Op302	Op303	Op304	Op305	Op306	Op307	Op308	Op309	Op310	Op311	Op312	Op313	Op314	Op315	Op316	Op317	Op318	Op319	Op320	Op321	Op322	Op323	Op324	Op325	Op326	Op327	Op328	Op329	Op330	Op331	Op332	Op333	Op334	Op335	Op336	Op337	Op338	Op339	Op340	Op341	Op342	Op343	Op344	Op345	Op346	Op347	Op348	Op349	Op350	Op351	Op352	Op353	Op354	Op355	Op356	Op357	Op358	Op359	Op360	Op361	Op362	Op363	Op364	Op365	Op366	Op367	Op368	Op369	Op370	Op371	Op372	Op373	Op374	Op375	Op376	Op377	Op378	Op379	Op380	Op381	Op382	Op383	Op384	Op385	Op386	Op387	Op388	Op389	Op390	Op391	Op392	Op393	Op394	Op395	Op396	Op397	Op398	Op399	Op400	Op401	Op402	Op403	Op404	Op405	Op406	Op407	Op408	Op409	Op410	Op411	Op412	Op413	Op414	Op415	Op416	Op417	Op418	Op419
----	----	-----	-----	-----	-----	-----	-----	-----	-----	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------	-------

```

2AB1 2471 .sbttl show_vcb, Display Volume Control Block (VCB)
2AB1 2472 :---
2AB1 2473 :
2AB1 2474 : show_vcb
2AB1 2475 :
2AB1 2476 : Display the Volume Control Block (VCB)
2AB1 2477 :
2AB1 2478 : Inputs:
2AB1 2479 :
2AB1 2480 : ap = Address of UCB in local storage
2AB1 2481 :
2AB1 2482 :---
2AB1 2483 :
2AB1 2484 show_vcb:
2AB1 2485 .word ^m<r2,r3,r4,r5,r11>
2AB3 2486
2AB3 2487 tctl ucb$l_vcb(ap) ; any VCB for this unit?
2AB6 2488 bneq 10$ ; Branch if so
2AB8 2489
2AB8 2490 90$: status success
2ABF 2491 ret
2AC0 2492
2AC0 2493 10$: bbs #dev$v_spl,ucb$l_devchar(ap),90$ ; ignore VCB for
2AC5 2494 ; spooled devices (wrong usage)
52 00000331'EF 9E 2AC5 2495 movab vcb,r2
2ACC 2496 getmem @ucb$l_vcb(ap),(r2),#vcb$c_length ; read entire VCB
2ADE 2497 blbc r0,90$
11 0A A2 91 2AE1 2498 cmpb vcb$b_type(r2),#dyn$c_vcb ; Check if block valid
D1 12 2AE5 2499 bneq 90$ ; Exit if not valid type
2AE7 2500
2AE7 2501 ensure 12
2AFF 2502 skip 1
34 AC DD 2B08 2503 pushl ucb$l_vcb(ap)
2B0B 2504 print 1,<!_!_--- Volume Control Block (VCB) !XL --->
2B18 2505 skip 1
2B21 2506 alloc 80 ; 80 byte output buffer
5B 5E D0 2B30 2507 movl sp, r11 ; save descriptor address
2B33 2508
2B33 2509 ; use different display stratagies for different VCB types
03 38 AC 0D E1 2B33 2510 bbc #dev$v_net, ucb$l_devchar(ap), 20$
028D 31 2B38 2511 brw vcb_net
2B3B 2512 20$: dispatch ucb$b_devclass(ap), type=B, prefix=dc$, <-
2B3B 2513 <disk,vcb_disk>, -
2B3B 2514 <tape,vcb_tape>, -
2B3B 2515 <journal,vcb_journal> -
2B3B 2516 >
2C83 2517 status success
04 2C8A 2518 ret
2C8B 2519
2C8B 2520 vcb_disk:
03 38 AC 18 E1 2C8B 2521 bbc #dev$v_for, - ; Is this a foreign mounted disk?
2C90 2522 ucb$l_devchar(ap), 20$
008A 31 2C90 2523 brw vcb_foreign ; Branch if foreign.
0080 C2 DF 2C93 2524 20$: pushal vcb$t_volcknam(r2) ; Address of volume lock name
OC DD 2C97 2525 pushl #12 ; Length of volume lock name
14 A2 DF 2C99 2526 pushal vcb$t_volname(r2) ; Address of volume name
OC DD 2C9C 2527 pushl #12 ; Length of volume name

```

```

    2C9E 2528      print      2,<Volume: !AD      Lock name: !AF>
    7E 5E 5B DO 2CAB 2529      movl      r11, sp      ; Setup scratch area
    DB22 CF 9A 2CAE 2530      movzbl     vcb$b_status(r2), -(sp) ; Volume status
    00000000'EF 02 FB 2CB2 2531      pushab   vcb_disk_status ; Bit definition table
    5E DD 2CB6 2532      calls      #2,-translate_bits ; Translate bits to names
    0B A2 DD 2CBD 2533      pushl      sp ; Address of output descriptor
    5E DD 2CBF 2534      pushl      vcb$b_status(r2)
    7E 5E 5B DO 2CC2 2535      print      2,<Status: !XB !AS>
    DB46 CF 9A 2CCF 2536      movl      r11, sp      ; Setup scratch area
    00000000'EF 02 FB 2CD2 2537      movzbl     vcb$b_status2(r2), -(sp) ; Volume status, second byte
    53 A2 DD 2CD6 2538      pushab   vcb_disk_status2 ; Bit definition table
    5E DD 2CDA 2539      calls      #2,-translate_bits ; Translate bits to names
    53 A2 DD 2CE1 2540      pushl      sp ; Address of output descriptor
    53 A2 DD 2CE3 2541      pushl      vcb$b_status2(r2)
    2CE6 2542      print      2,<Status2: !XB !AS>
    2CF3 2543      skip      1
    2CFC 2544      print_columns -
    2CFC 2545      (r2), ucb$l_vcb(ap), -
    2CFC 2546      vcb_disk_col_1, vcb_disk_col_2, vcb_disk_col_3
    0129 31 2D1A 2547      brw      vcb_show_acpq
    2D1D 2548
    2D1D 2549      .enable lsb
    2D1D 2550      vcb_tape:
    2D1D 2551      vcb_foreign:
    14 A2 DF 2D1D 2552      pushal     vcb$t_volname(r2) ; Address of volume name
    0C DD 2D20 2553      pushl      #12 ; Length of volume name
    22 38 AC 18 E1 2D22 2554      print      1,<Volume: !AD>
    2D2F 2555      bbc      #dev$v_for, - ; Is this a foreign mounted volume?
    2D34 2556      ucb$l_devchar(ap), 20$ ; Branch if not foreign.
    2D34 2557      skip      1
    2D3D 2558      print      0,<!_!_!_Volume is foreign mounted>
    2D4A 2559      skip      1
    00F0 31 2D53 2560      brw      vcb_show_acpq ; Go try to do AQB, ha ha.
    7E 5E 5B DO 2D56 2561      20$: movl      r11, sp ; Setup scratch area
    DBAEF CF 9A 2D59 2562      movzbl     vcb$b_status(r2), -(sp) ; Volume status
    00000000'EF 02 FB 2D5D 2563      pushab   vcb_tape_status ; Bit definition table
    5E DD 2D61 2564      calls      #2,-translate_bits ; Translate bits to names
    0B A2 DD 2D68 2565      pushl      sp ; Address of output descriptor
    5E DD 2D6A 2566      pushl      vcb$b_status(r2)
    7E 5E 5B DO 2D6D 2567      print      2,<Status: !4XB !AS>
    DB13 CF 9A 2D7A 2568      movl      r11, sp ; Setup scratch area
    00000000'EF 02 FB 2D7D 2569      movzwl     vcb$w_mode(r2), -(sp) ; Volume operating mode
    2C A2 DD 2D81 2570      pushab   vcb_tape_mode ; Bit definition table
    5E DD 2D85 2571      calls      #2,-translate_bits ; Translate bits to names
    2C A2 DD 2D8C 2572      pushl      sp ; Address of output descriptor
    2D8E 2573      pushl      vcb$w_mode(r2)
    2D91 2574      print      2,<Mode: !4XW !AS>
    2D9E 2575      skip      1
    2DA7 2576      print_columns -
    2DA7 2577      (r2), ucb$l_vcb(ap), -
    007E 31 2DA7 2578      vcb_tape_col_1, vcb_tape_col_2, vcb_tape_col_3
    2DC5 2579      brw      vcb_show_acpq
    2DC8 2580
    2DC8 2581      .disable lsb
    2DC8 2582
    2DC8 2583      vcb_net:
    2DC8 2584      print_columns -
```

Display device data structures 16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
show_vcb, Display Volume Control Block (5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 57
(17)

Address	Disassembly	Comment
005D 31	brw	(r2), ucb\$l_vcb(ap), - vcb_net_col_1, vcb_net_col_2, vcb_net_col_3 vcb_show_acpq
14 A2 DF	pushal	vcb\$j_tvolname(r2) ; Address of journalname
OC DD	pushl	#12 ; Length of journal name
5E 5B DO	print	1,<Journal name: !AD>
7E 24 A2 DO	movl	r11, sp ; Setup scratch area
DB02 CF 9F	movl	vcb\$l_jnl_char(r2),-(sp); Journal characteristics
00000000'EF 02 FB	pushab	vcb_journal_char ; Bit definition table
5E DD	calls	#2,-translate_bits ; Translate bits to names
24 A2 DD	pushl	sp ; Address of output descriptor
	pushl	vcb\$l_jnl_char(r2)
	print	2,<Characteristics: !XL !AS>
	skip	1
	print_columns -	
	(r2), ucb\$l_vcb(ap), -	
	vcb_jnl_col_1, vcb_jnl_col_2, vcb_jnl_col_3	
F768 CF 62 FA	vcb_show_acpq:	
04	callg	(r2),show_acpq ; Display ACP queue (if any)
	ret	

[illegible]

```

2E4C 2609      .sbttl volume control block tables & action routines
2E4C 2610
2E4C 2611      : The following are all PRINT_COLUMNS action routines for the show_vcb
2E4C 2612      : block displays.
2E4C 2613
2E4C 2614      : Action Routine Inputs:
2E4C 2615
2E4C 2616      : R2          value from the COLUMN_LIST entry
2E4C 2617      : R5          size of value section for this item
2E4C 2618      : R7          address of a descriptor for a scratch string in
2E4C 2619      :          which the FA0 converted value is to be returned
2E4C 2620      : R11         base address of the local UCB copy
2E4C 2621
2E4C 2622      : Action Routine Outputs:
2E4C 2623
2E4C 2624      : R0          status
2E4C 2625      :          lbs ==> use this entry
2E4C 2626      :          lbc ==> skip this entry
2E4C 2627      : R1 - R5     scratch
2E4C 2628      :          all other registers must be preserved
2E4C 2629
2E4C 2630
2E4C 2631      : PRINT_COLUMNS tables for disk VCB displays
2E4C 2632
2E4C 2633      :
2E4C 2634      : vcb_disk_col_1:
2E4C 2635      : column_list -
2E4C 2636      : vcb$, 16, 8, 4, < -
2E4C 2637      : <<Mount count>,w_mcount,uw>, -
2E4C 2638      : <<Transactions>,w_trans,uw>, -
2E4C 2639      : <<Free blocks>,l_free,ul>, -
2E4C 2640      : <<Window size>,b_window,ub>, -
2E4C 2641      : <<Vol. lock ID>,l_vollkid,xl_neq>, -
2E4C 2642      : <<Block. lock ID>,l_blockid,xl_neq>, -
2E4C 2643      : >
2E4C 2644
2EBC 2645      : vcb_disk_col_2:
2EBC 2646      : column_list -
2EBC 2647      : vcb$, 16, 8, 4, < -
2EBC 2648      : <<Rel. volume>,w_rvn,uw>, -
2EBC 2649      : <<Max. files>,l_maxfiles,ul>, -
2EBC 2650      : <<Rsvd. files>,b_resfiles,ub>, -
2EBC 2651      : <<Cluster size>,w_cluster,uw>, -
2EBC 2652      : <<Def. extend sz>,w_extend,uw>, -
2EBC 2653      : <<Record size>,w_recordsz,uw>, -
2EBC 2654      : >
2EBC 2655
2F2C 2656      : vcb_disk_col_3:
2F2C 2657      : column_list -
2F2C 2658      : vcb$, 16, 8, 0, < -
2F2C 2659      : <<AOB address>,l_aob,xl>, -
2F2C 2660      : <<RVT address>,l_rvt,xl>, -
2F2C 2661      : <<FCB queue>,l_fcbl,q2>, -
2F2C 2662      : <<Quota FCB>,l_quota_fcb,xl_neq>, -
2F2C 2663      : <<Quota cache>,l_quocache,xl_neq>, -
2F2C 2664      : <<Cache blk.>,l_cache,xl_neq>, -
2F2C 2665

```

```

2F2C 2666 >
2F9C 2667
2F9C 2668 :
2F9C 2669 :: PRINT_COLUMNS tables for tape VCB displays
2F9C 2670 :
2F9C 2671
2F9C 2672 vcb_tape_col_1:
2F9C 2673     column_list -
2F9C 2674         vcb$, 16, 8, 4, < -
2F9C 2675         <<Transactions>,w_trans,uw>, -
2F9C 2676         <<Start record>,l_st_record,ul>, -
2F9C 2677         <<Tapemark count>,b_fm,ub>, -
2F9C 2678         >
2FDC 2679
2FDC 2680 vcb_tape_col_2:
2FDC 2681     column_list -
2FDC 2682         vcb$, 16, 8, 4, < -
2FDC 2683         <<Rel. volume>,b_cur_rvn,ub>, -
2FDC 2684         <<Tape vol. list>,l_mv1,xl_neq>, -
2FDC 2685         >
300C 2686
300C 2687 vcb_tape_col_3:
300C 2688     column_list -
300C 2689         vcb$, 16, 8, 0, < -
300C 2690         <<AQB address>,l_aqb,xl>, -
300C 2691         <<Virt. pg. queue>,l_vpfl,q2>, -
300C 2692         <<Blocked queue>,l_blockfl,q2>, -
300C 2693         >
304C 2694
304C 2695 :
304C 2696 :: PRINT_COLUMNS tables for network VCB displays
304C 2697 :
304C 2698
304C 2699 vcb_net_col_1:
304C 2700     column_list -
304C 2701         vcb$, 16, 8, 4, < -
304C 2702         <<Transactions>,w_trans,uw>, -
304C 2703         >
306C 2704
306C 2705 vcb_net_col_2:
306C 2706     column_list -
306C 2707         vcb$, 16, 8, 4, < -
306C 2708         <<Mount count>,w_mcount,uw>, -
306C 2709         >
308C 2710
308C 2711 vcb_net_col_3:
308C 2712     column_list -
308C 2713         vcb$, 16, 8, 0, < -
308C 2714         <<AQB address>,l_aqb,xl>, -
308C 2715         >
30AC 2716
30AC 2717 :
30AC 2718 :: PRINT_COLUMNS tables for journal VCB displays
30AC 2719 :
30AC 2720
30AC 2721 vcb_jnl_col_1:
30AC 2722     column_list -

```

[illegible]

DEVICE
V04-000

Display device data structures 16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
volume control block tables & action rou 5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 60
(17)

```

30AC 2723          vcb$, 16, 8, 4, < -
30AC 2724          <<Copies>,w_jnl_cop,uw>, -
30AC 2725          <<Mask>,l_jnl_mask,xl>, -
30AC 2726          >
30DC 2727
30DC 2728 vcb_jnl_col_2:
30DC 2729         column_list -
30DC 2730         vcb$, 16, 8, 4, < -
30DC 2731         <<Access mode>,b_jnl_mode,xl>, -
30DC 2732         <<JFT address>,l_jnl_jfta,xl>, -
30DC 2733         >
310C 2734
310C 2735 vcb_jnl_col_3:
310C 2736         column_list -
310C 2737         vcb$, 16, 8, 0, < -
310C 2738         <<AQB address>,l_aqb,xl>, -
310C 2739         <<JMT address>,l_jnl_jmt,xl>, -
310C 2740         >

```

B
C
D
E
F
G
H
I
J
K
L
M
N
O
P
Q
R
S
T
U
V
W
X
Y
Z

```
313C 2742 .sbttl show_cddb, Display Class Driver Data Block (CDDb)
313C 2743 :---
313C 2744 :
313C 2745 show_cddb
313C 2746 :
313C 2747 Display the Class Driver Data Block (CDDb)
313C 2748 :
313C 2749 Inputs:
313C 2750 :
313C 2751 ap = Address of UCB in local storage
313C 2752 r6 = actual address of cddb
313C 2753 :
313C 2754 :---
313C 2755
313C 2756 show_cddb:
083C 313C 2757 .word ^m<r2,r3,r4,r5,r11>
313E 2758
313E 2759 tstl r6 ; is there a cddb
23 13 3140 2760 beql 5$ ; no, so exit
52 00000471'EF 9E 3142 2761 movab cddb, r2 ; store address of local cddb
08 50 E9 3149 2762 getmem (r6), (r2), #cddb$c_length ; read entire cddb
315A 2763 blbc r0, 5$ ; return if not able to read it
0A A2 0164 8F B1 315D 2764 cmpw #<dyn$c_cd_cddb+dyn$c_classdrv>, cddb$b_type(r2)
3163 2765 ; check for valid block type
08 13 3163 2766 beql 10$ ; exit if not valid type
3165 2767 5$:
3165 2768 status success ;
3165 2769 ret
04 316C 2770
316D 2771
316D 2772 10$: ensure 20 ; need 15 lines for this display
3185 2773 skip 1 ; advance 1 line
56 DD 318E 2774 pushl r6 ; pass address of cddb to print routine
00000575'EF B5 3190 2775 tstw flag_2nd_cddb ; 0 - primary, 1 - secondary
0F 12 3196 2776 bneq second ; secondary if branch
0D 11 3198 2777 print 1, <!-- Primary Class Driver Data Block (CDDb) !XL --->
31A5 2778 brb display
31A7 2779 second:
31A7 2780 print 1, <!-- Secondary Class Driver Data Block (CDDb) !XL --->
31B4 2781 display:
31B4 2782 skip 1 ; advance 1 line
5B 5E D0 31BD 2783 movl sp, r11 ; save pre-allocation stack pointer
7E 12 A2 3C 31C0 2784 alloc 80, r4 ; 80 byte output buffer
D74E CF 9F 31D2 2785 movzwl cddb$b_status(r2), -(sp) ; cddb status field
00000000'EF C2 FB 31D6 2786 pushab cddb_sflags ; bit definition table
54 DD 31E1 2787 calls #2, translate_bits ; translate bits to names
7E 12 A2 3C 31E3 2788 pushl r4 ; address of output descriptor
31E7 2789 movzwl cddb$b_status(r2), -(sp) ; pass value of status field to print
64 50 8F 9A 31F4 2790 print 2, <Status: !XW !AS> ; display status
7E 28 A2 3C 31F8 2791 movzbl #80, (r4) ;
D790 CF 9F 31FC 2792 movzwl cddb$b_cntrlflgs(r2), -(sp) ; cddb controller flags
00000000'EF 02 FB 3200 2793 pushab cddb_fflags ; bit definition table
54 DD 3207 2794 calls #2, translate_bits ; translate bits to names
7E 28 A2 3C 3209 2795 pushl r4 ; address of output descriptor
5E 5B D0 320D 2796 movzwl cddb$b_cntrlflgs(r2), -(sp) ; pass value of status field to print
320D 2797 print 2, <Controller Flags: !XW !AS> ; display status
321A 2798 movl r11, sp ; restore stack pointer
```


DEVICE
V04-000

Display device data structures C 16
show_cddb, Display Class Driver Data Blo 16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 62
(18)

```
04 321D 2799 skip 1 ; advance 1 line
    3226 2800 print_columns -
    3226 2801 (r2), r6, -
    3226 2802 cddb_col_1, cdub_col_2, cddb_col_3 ;display!!!!
    3243 2803 status success
    324A 2804 ret
    324B 2805
    324B 2806
```

```

3248 2808      .sbtcl class driver data block tables & action routines
3248 2809
3248 2810      ; The following are all PRINT_COLUMNS action routines for the show_cddb
3248 2811      ; block displays.
3248 2812      ;
3248 2813      ; Action Routine Inputs:
3248 2814      ;
3248 2815      ; R2          value from the COLUMN_LIST entry
3248 2816      ; R5          size of value section for this item
3248 2817      ; R7          address of a descriptor for a scratch string in
3248 2818      ;              which the FAO converted value is to be returned
3248 2819      ; R11         base address of the local UCB copy
3248 2820      ;
3248 2821      ; Action Routine Outputs:
3248 2822      ;
3248 2823      ; R0          status
3248 2824      ;              lbs ==> use this entry
3248 2825      ;              lbc ==> skip this entry
3248 2826      ; R1 - R5    scratch
3248 2827      ;              all other registers must be preserved
3248 2828      ;
3248 2829      ;
3248 2830      ; PRINT_COLUMNS tables for Cddb displays
3248 2831      ;
3248 2832      ;
3248 2833      ; cddb_col_1:
3248 2834      ; column_list -
3248 2835      ; cddb$, 16, 8, 4, < -
3248 2836      ; <<Allocation class>,l_alloccls,ul>, -
3248 2837      ; <<System ID>,cddb_4bytes,cddb$b_systemid>, -
3248 2838      ; <<>,cddb_2bytes,cddb$b_systemid+4>,-
3248 2839      ; <<Contrl. ID>,cddb_4bytes,cddb$q_cntrlid>, -
3248 2840      ; <<>,cddb_4bytes,cddb$q_cntrlid+4>,-
3248 2841      ; <<Response ID>,l_oldrspid,xl>, -
3248 2842      ; <<MSCP Cmd status>,l_oldcmdsts,xl>,-
3248 2843      ; >
3248 2844      ;
3248 2845      ; cddb_col_2:
3248 2846      ; column_list -
3248 2847      ; cddb$, 16, 8, 4, < -
3248 2848      ; <<CDRP Queue>,l_cdrpqfl,q2>, -
3248 2849      ; <<Restart Queue>,l_rstrtqfl,q2>, -
3248 2850      ; <<Restarted CDRP>,rstrt_cdrp,cddb$l_rstrtcdrp>, -
3248 2851      ; <<CDRP retry cnt.>,retry_cnt,cddb$b_retrycnt>, -
3248 2852      ; <<DAP Count>,b_dapcount,ub>, -
3248 2853      ; <<Contr. timeout>,w_cntrltno,uw>, -
3248 2854      ; <<Reinit Count>,w_rstrtcnt,uw>, -
3248 2855      ; <<Wait UCB Count>,w_wtucbctr,uw>, -
3248 2856      ; >
3248 2857      ;
3248 2858      ; cddb_col_3:
3248 2859      ; column_list -
3248 2860      ; cddb$, 16, 8, 0, < -
3248 2861      ; <<DDB address>,l_ddb,xl>, -
3248 2862      ; <<CRB address>,l_crb,xl>, -
3248 2863      ; >
3248 2864

```

```

335B 2865 <<CDDb link>,l_cddblink,xl>, -
335B 2866 <<PDT address>,l_pdt,xl>, -
335B 2867 <<Original UCB>,l_origucb,xl>,-
335B 2868 <<UCB chain>,l_ucbchain,xl>, -
335B 2869 >
33CB 2870
33CB 2871 ;*****
33CB 2872 cddb_4bytes:
53 5B 52 C1 33CB 2873 addl3 r2,r11,r3 ; locate storage of interest
55 08 C2 33CF 2874 subl #8,r5 ; get size of filler field
33D2 2875 $fao_s -
33D2 2876 ctrstr=cddb_fao,-
33D2 2877 outbuf = (r7),-
33D2 2878 outlen = (r7),-
33D2 2879 p1 = r5,-
33D2 2880 p2 = (r3)
05 33E7 2881 rsb
33E8 2882
33E8 2883 ;*****
33E8 2884 cddb_2bytes:
53 5B 52 C1 33E8 2885 addl3 r2, r11, r3 ; locate storage of interest
55 04 C2 33EC 2886 subl #4, r5 ; get size of filler field
33EF 2887 $fao_s -
33EF 2888 ctrstr = sb_fao_6bytes, -
33EF 2889 outbuf = (r7), -
33EF 2890 outlen = (r7), -
33EF 2891 p1 = r5, -
33EF 2892 p2 = (r3)
05 3404 2893 rsb
3405 2894
3405 2895 ;*****
OC 12 AB 00 E1 3405 2896 rstrt_cdrp:
3405 2897 bbc #cddb$v_snglstrm,cddb$w_status(r11),cddb_act_nop
52 5B C0 340A 2898 ; cdrp only exists if single stream
340A 2899 addl r11,r2 ; locate cell to return
340D 2900 do_column_entry xl,jmp ; display this entry
3416 2901
3416 2902 cddb_act_nop:
50 D4 3416 2903 clrl r0
05 3418 2904 rsb
3419 2905
3419 2906 ;*****
F8 12 AB 00 E1 3419 2907 retry_cnt:
341E 2908 bbc #cddb$v_snglstrm,cddb$w_status(r11),cddb_act_nop
52 5B C0 341E 2909 ; count is valid if single stream
3421 2910 addl r11,r2 ; locate cell to return
342A 2911 do_column_entry ub,jmp ; display this entry
342A 2912

```

DEVICE
V04-000

Display device data structures F 16
class driver data block tables & action
342A 2914 .end

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 65
(20)

DEVICE
Symbol table

Display device data structures

G 16

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 66
(20)

\$\$\$	= 00000871	R	04	CDDBSL_ALLOCLS	= 00000050		
\$\$TMP1	= 00000001			CDDBSL_CDDBLINK	= 00000058		
\$\$TMP2	= 000000EF			CDDBSL_CDRPQFL	= 00000000		
\$\$BASE	= 00000001			CDDBSL_CRB	= 00000018		
\$\$DISPL	= 000000A2			CDDBSL_DDB	= 0000001C		
\$\$GENSW	= 00000001			CDDBSL_OLDCMDST;	= 00000030		
\$\$HIGH	= 000000A1			CDDBSL_OLDRSPIC	= 0000002C		
\$\$LIMIT	= 000000A0			CDDBSL_ORIGUCB	= 0000004C		
\$\$LOW	= 00000001			CDDBSL_PDT	= 00000014		
\$\$MNSW	= 00000001			CDDBSL_RSTRICDRP	= 00000034		
\$\$MXSW	= 00000001			CDDBSL_RSTRICQFL	= 0000003C		
\$\$T2	= 00000005			CDDBSL_UCBCHAIN	= 00000048		
ACP_STATUS	= 00000B98	R	03	CDDBSQ_CNTRLID	= 00000020		
ADD_SYMBOL	*****	X	03	CDDBSV_2PBSY	= 0000000B		
ADPSW_ADPTYPE	= 0000000E			CDDBSV_ALCLS_SET	= 00000006		
AQB	= 0000041D	R	02	CDDBSV_DAPBSY	= 0000000A		
AQBSB_ACPTYPE	= 00000015			CDDBSV_IMPEN	= 00000001		
AQBSB_CLASS	= 00000016			CDDBSV_INITING	= 00000002		
AQBSB_MNTCNT	= 0000000B			CDDBSV_NOCONN	= 00000007		
AQBSB_STATUS	= 00000014			CDDBSV_POLLING	= 00000005		
AQBSB_LENGTH	= 0000001C			CDDBSV_QUORLOST	= 00000009		
AQBSK_F11V1	= 00000001			CDDBSV_RECONNECT	= 00000003		
AQBSK_F11V2	= 00000002			CDDBSV_RESYNCH	= 00000004		
AQBSK_JNL	= 00000006			CDDBSV_RSTRICWAIT	= 00000008		
AQBSK_MTA	= 00000003			CDDBSV_SINGLSTRM	= 00000000		
AQBSK_NET	= 00000004			CDDBSW_CNTRLFLGS	= 00000028		
AQBSK_REM	= 00000005			CDDBSW_CNTRLTMO	= 0000002A		
AQBSK_UNDEFINED	= 00000000			CDDBSW_RSTRICNT	= 0000003A		
AQBSL_ACPPID	= 0000000C			CDDBSW_STATUS	= 00000012		
AQBSL_ACPQFL	= 00000000			CDDBSW_WTUCBCTR	= 0000005E		
AQBSL_LINK	= 00000010			CDDB_2BYTES	= 000033E8	R	03
AQBSV_CREATING	= 00000003			CDDB_2P	= 000004E1	R	02
AQBSV_DEFCCLASS	= 00000001			CDDB_4BYTES	= 000033CB	R	03
AQBSV_DEFSYS	= 00000002			CDDB_ACT_NOP	= 00003416	R	03
AQBSV_UNIQUE	= 00000000			CDDB_COL_1	= 0000324B	R	03
AQB_ACPTYPE	= 00000BC0	R	03	CDDB_COL_2	= 000032CB	R	03
AQB_CLASS	= 000027F7	R	03	CDDB_COL_3	= 0000335B	R	03
AQB_COLUMN_1	= 0000274D	R	03	CDDB_FAO	= 00000E12	R	04
AQB_COLUMN_2	= 0000276D	R	03	CDDB_FLAGS	= 00000990	R	03
AQB_COLUMN_3	= 0000279D	R	03	CDDB_STATUS	= 00000928	R	03
AQB_TYPE	= 000027CD	R	03	CDRP	= 00000289	R	02
ARGS	= 00000003			CDRPSB_EFN	= FFFFFFFC2		
AT\$_UBA	= 00000001			CDRPSB_RMOD	= FFFFFFFAB		
BAD_ASCIC	= 00000E36	R	04	CDRPSB_CD_LEN	= 00000048		
BIT...	= 00000003			CDRPSL_AST	= FFFFFFFB0		
BUFFER	*****	X	03	CDRPSL_DUTUFLGS	= 00000040		
BUS_TYPE	= 00000728	R	03	CDRPSL_FQFL	= 00000000		
CARD_TYPE	= 00000548	R	03	CDRPSL_IOQFL	= FFFFFFFA0		
CBL_A_ASCIC	= 00000E2C	R	04	CDRPSL_IOSB	= FFFFFFFC4		
CBL_B_ASCIC	= 00000E2F	R	04	CDRPSL_PID	= FFFFFFFAC		
CDDB	= 00000471	R	02	CDRPSL_UCB	= FFFFFFFBC		
CDDBSB_DAPCOUNT	= 00000039			CDRPSL_WIND	= FFFFFFFB8		
CDDBSB_RETRYCNT	= 00000038			CDRPSV_CAND	= 00000000		
CDDBSB_SYSTEMID	= 0000000C			CDRPSV_CANIO	= 00000001		
CDDBSB_TYPE	= 0000000A			CDRPSV_ERLIP	= 00000002		
CDDBSB_LENGTH	= 00000070			CDRPSV_HIRT	= 00000004		
CDDBSK_LENGTH	= 00000070			CDRPSV_IVCMD	= 00000008		

DEVICE
Symbol table

Display device data structures

H 16

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 67
(20)

```

CDRPSV_PERM      = 00000003
CDRPSW_CHAN      = FFFFFFFC8
CDRPSW_FUNC      = FFFFFFFC0
CDRPSW_STS       = FFFFFFFCA
CDRP_DOTUFLAGS   = 000009D8 R    03
CDRP_HEADING     = 000029B9 R    03
CDRP_LENGTH      = 000000A8
CMND_BUFFER      = ***** X    03
CMND_DESCR       = ***** X    03
COLMSK_FAO_AC    = 00000000
COLMSK_FAO_AS    = 00000001
COLMSK_FAO_OW    = 00000007
COLMSK_FAO_Q2    = 00000011
COLMSK_FAO_UB    = 00000005
COLMSK_FAO_UL    = 0000000F
COLMSK_FAO_UW    = 0000000A
COLMSK_FAO_XB    = 00000003
COLMSK_FAO_XL    = 0000000D
COLMSK_FAO_XL_NEQ = 0000008D
COLMSK_FAO_XW    = 00000008
COLMSK_LENGTH    = 00000010
CRBSK_LENGTH     = 00000048
CRBSL_AUXSTRUC   = 00000010
CRBSL_DUE TIME   = 00000018
CRBSL_INTD       = 00000024
CRBSL_LINK       = 00000020
CRBSL_TIMELINK   = 00000014
CRBSL_TOUTROUT   = 0000001C
CRBSL_WQFL       = 00000000
CRBSW_REFC       = 0000000C
CRB_COLUMN_1     = 000013F0 R    03
CRB_COLUMN_2     = 00001420 R    03
CRB_COLUMN_3     = 00001450 R    03
CRB_DEVCLASS     = 00000578 R    02
CRB_TIMEOUT      = 00001480 R    03
CROSSED_ASCII    = 00000E3A R    04
DCS_BUS          = 00000080
DCS_CARD         = 00000041
DCS_DISK         = 00000001
DCS_JOURNAL      = 000000A1
DCS_LP           = 00000043
DCS_MAILBOX      = 000000A0
DCS_MISC         = 000000C8
DCS_REALTIME     = 00000060
DCS_SCOM         = 00000020
DCS_TAPE         = 00000002
DCS_TERM         = 00000042
DCS_WORKSTATION  = 00000046
DDB              = 00000071 R    02
DDB$B_ACPCLASS   = 00000013
DDB$B_TYPE       = 0000000A
DDB$C_LENGTH     = 00000044
DDB$K_CART       = 00000002
DDB$K_LENGTH     = 00000044
DDB$K_PACK       = 00000001
DDB$K_SLOW       = 00000003
DDB$K_TAPE       = 00000004

```

```

DDB$L_ACPD       = 00000010
DDB$L_ALLOCLS    = 0000003C
DDB$L_CONLINK    = 00000038
DDB$L_DDT        = 0000000C
DDB$L_DP_UCB     = 00000040
DDB$L_LINK       = 00000000
DDB$L_SB         = 00000034
DDB$L_UCB        = 00000004
DDB$T_DRVNAME    = 00000024
DDB$T_NAME       = 00000014
DDB_2P          = 000000B5 R    02
DDB_ACPCLASS     = 00000090 R    03
DDB_ACPCLS       = 000013C4 R    03
DDB_ACPD         = 0000139E R    03
DDB_COLUMN_1     = 000012DE R    03
DDB_COLUMN_2     = 0000131E R    03
DDB_COLUMN_3     = 0000135E R    03
DDB_NO_ACP       = 000013C1 R    03
DDT$K_LENGTH     = 00000038
DDT$L_ALTSTART   = 0000001C
DDT$L_CANCEL     = 0000000C
DDT$L_CLONEDUCB  = 00000024
DDT$L_FDT        = 00000008
DDT$L_MNTVER     = 00000020
DDT$L_REGDUMP    = 00000010
DDT$L_START      = 00000000
DDT$L_UNITINIT   = 00000018
DDT$L_UNSLINT    = 00000004
DDT$W_DIAGBUF    = 00000014
DDT$W_ERRORBUF   = 00000016
DDT$W_FDT_SIZE   = 00000028
DDT_ADDRESS      = 000017B3 R    03
DDT_COLUMN_1     = 000016C3 R    03
DDT_COLUMN_2     = 00001713 R    03
DDT_COLUMN_3     = 00001763 R    03
DDT_RETURN       = 00000B79 R    04
DEFINE_UCB_SYMBOLS = 00001E6A R    03
DEV$M_2P         = 00000010
DEV$M_DMT        = 00200000
DEV$M_MBX        = 00100000
DEV$M_MNT        = 00080000
DEV$M_NET        = 00002000
DEV$V_2P         = 00000004
DEV$V_ALL        = 00000017
DEV$V_AVL        = 00000012
DEV$V_CCL        = 00000001
DEV$V_CDP        = 00000003
DEV$V_CLU        = 00000000
DEV$V_DET        = 00000001
DEV$V_DIR        = 00000003
DEV$V_DMT        = 00000015
DEV$V_DUA        = 0000000F
DEV$V_EL6        = 00000016
DEV$V_FOD        = 0000000E
DEV$V_FOR        = 00000018
DEV$V_GEN        = 00000011
DEV$V_IDV        = 0000001A

```

DEVICE
Symbol table

Display device data structures

I 16

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 68
(20)

DEVSU_MBX	= 00000014			DTS-DN11	= 00000001
DEVSU_MNT	= 00000013			DTS-DR11C	= 00000007
DEVSU_MSCP	= 00000005			DTS-DR11W	= 00000004
DEVSU_NET	= 00000000			DTS-DR750	= 00000003
DEVSU_NNM	= 00000009			DTS-DR780	= 00000002
DEVSU_ODV	= 00000018			DTS-DZ11	= 00000042
DEVSU_OPR	= 00000007			DTS-DZ32	= 00000043
DEVSU_RCK	= 0000001E			DTS-DZ730	= 00000044
DEVSU_RCT	= 00000008			DTS-FT1	= 00000010
DEVSU_REC	= 00000000			DTS-FT2	= 00000011
DEVSU_RED	= 00000008			DTS-FT3	= 00000012
DEVSU_RND	= 0000001C			DTS-FT4	= 00000013
DEVSU_RTM	= 0000001D			DTS-FT5	= 00000014
DEVSU_RTT	= 00000002			DTS-FT6	= 00000015
DEVSU_SDI	= 00000004			DTS-FT7	= 00000016
DEVSU_SHR	= 00000010			DTS-FT8	= 00000017
DEVSU_SPL	= 00000006			DTS-IX_IEX11	= 0000000A
DEVSU_SQD	= 00000005			DTS-LAT1	= 00000002
DEVSU_SRV	= 00000007			DTS-LA12	= 00000024
DEVSU_SSM	= 00000006			DTS-LA120	= 00000021
DEVSU_SWL	= 00000019			DTS-LA180	= 00000003
DEVSU_TRM	= 00000002			DTS-LA24	= 00000025
DEVSU_WCK	= 0000001F			DTS-LA34	= 00000022
DEVICE_CHAR	00000160	R	03	DTS-LA36	= 00000020
DEVICE_CHAR_2	00000248	R	03	DTS-LA38	= 00000023
DEVICE_CLASS	000002A0	R	03	DTS-LAX	= 00000020
DISK_TYPE	00000308	R	03	DTS-LES1	= 00000005
DISPLAY	000031B4	R	03	DTS-LP11	= 00000001
DISPLAY_DDT	00001275	R	03	DTS-LPA11	= 00000001
DISPLAY_DEVBYADDR	00000C00	RG	03	DTS-LQP02	= 00000026
DISPLAY_DEVICE	00000CE2	RG	03	DTS-MBX	= 00000001
DO_UCB_COLUMNS	00001F25	R	03	DTS-ML11	= 00000011
DPT	00000439	R	02	DTS-MX_MUX200	= 00000008
DPTSC_LENGTH	= 00000038			DTS-NI	= 00000000
DPTSL_FLINK	= 00000000			DTS-NULL	= 00000003
DPTST_NAME	= 00000020			DTS-NV_X29	= 00000006
DPTSW_SIZE	= 00000008			DTS-NW_X25	= 00000005
DTS-ATJNL	= 00000003			DTS-PCC11R	= 00000005
DTS-ATJNL	= 00000004			DTS-PCL11T	= 00000006
DTS-BIJNL	= 00000002			DTS-RA60	= 00000016
DTS-CI	= 0000000C			DTS-RA80	= 00000014
DTS-CI750	= 00000002			DTS-RA81	= 00000015
DTS-CI780	= 00000001			DTS-RA82	= 0000001E
DTS-CLJNL	= 00000005			DTS-RB02	= 00000012
DTS-CR11	= 00000001			DTS-RB80	= 00000013
DTS-CRX50	= 00000021			DTS-RC25	= 00000017
DTS-DELUA	= 00000019			DTS-RC26	= 0000001F
DTS-DEQNA	= 00000016			DTS-RCF25	= 00000018
DTS-DEUNA	= 0000000E			DTS-RCF26	= 00000020
DTS-DHU	= 00000047			DTS-RD26	= 0000001D
DTS-DHV	= 00000046			DTS-RD51	= 00000019
DTS-DMC11	= 00000001			DTS-RD52	= 0000001B
DTS-DMF32	= 0000000A			DTS-RD53	= 0000001C
DTS-DMP11	= 00000009			DTS-RDRX	= 00000007
DTS-DMR11	= 00000002			DTS-RK06	= 00000001
DTS-DMV11	= 00000017			DTS-RK07	= 00000002
DTS-DMZ32	= 00000045			DTS-RL01	= 00000009

DEVICE
Symbol table

Display device data structures

J 16

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 69
(20)

```

DTS-RL02      = 0000000A
DTS-RM03      = 00000006
DTS-RM05      = 0000000F
DTS-RM80      = 0000000D
DTS-RO04      = 00000003
DTS-RO05      = 00000004
DTS-RO06      = 00000005
DTS-RO07      = 00000007
DTS-RO07HT    = 00000008
DTS-RUJNL     = 00000001
DTS-RX01      = 00000010
DTS-RX02      = 0000000B
DTS-RX04      = 0000000C
DTS-RX50      = 0000001A
DTS-RZ01      = 00000017
DTS-RZF01     = 00000018
DTS-SB-1SB11  = 00000007
DTS-SHRMBX    = 00000002
DTS-TA78      = 00000006
DTS-TA81      = 00000009
DTS-TE16      = 00000001
DTS-TEK401X   = 0000000A
DTS-TK50      = 0000000A
DTS-TQ-BTS    = 00000004
DTS-TST1      = 00000004
DTS-TTYUNKN   = 00000000
DTS-TU45      = 00000002
DTS-TU58      = 0000000E
DTS-TU77      = 00000003
DTS-TU78      = 00000005
DTS-TU80      = 00000007
DTS-TU81      = 00000008
DTS-TU81P     = 00000006
DTS-UDA50     = 00000003
DTS-UDA50A    = 00000004
DTS-UK-KTC32  = 00000015
DTS-UQPORT    = 00000003
DTS-VK100     = 00000002
DTS-VS100     = 00000001
DTS-VS125     = 00000002
DTS-VS300     = 00000003
DTS-VT05      = 00000001
DTS-VT100     = 00000060
DTS-VT101     = 00000061
DTS-VT102     = 00000062
DTS-VT105     = 00000063
DTS-VT125     = 00000064
DTS-VT131     = 00000065
DTS-VT132     = 00000066
DTS-VT173     = 00000003
DTS-VT52      = 00000040
DTS-VT55      = 00000041
DTS-VT5X      = 00000040
DTS-XI-DR11C  = 0000000D
DTS-XJ-2780   = 00000004
DTS-XK-3271   = 00000003
DTS-XP-PCL11B = 00000009

```

```

DTS-XV-3271   = 0000000B
DTS-YN-X25    = 0000000F
DTS-YO-X25    = 00000010
DTS-YP-ADCCP  = 00000011
DTS-YQ-3271   = 00000012
DTS-YR-DDCMP  = 00000013
DTS-YS-SDLC   = 00000014
DYN$C-CD-CDDB = 00000001
DYN$C-CLASSDRV = 00000064
DYN$C-DDB     = 00000006
DYN$C-SCS     = 00000060
DYN$C-SCS-PDT = 00000005
DYN$C-SCS-SB  = 00000007
DYN$C-UCB     = 00000010
DYN$C-VCB     = 00000011
END PB        = 00001913 R      03
FAB$-STV      = ***** X    03
FIND-DPT      = 00000EB7 R    03
FLAG-2ND-CDDB = 00000575 R    02
FLAG-M-ACT-PATH = 00000002
FLAG-M-FND-UNIT = 00000004
FLAG-M-ONE-UNIT = 00000001
FLAG-V-ALT-PATH = 00000001
FLAG-V-FND-UNIT = 00000002
FLAG-V-ONE-UNIT = 00000000
FOUND-DPT     = 000008D2 R      04
GETMEM        = ***** X    03
GET-DDB       = 00000F05 R    03
GET-UCB       = 00001F89 R    03
IDB$B-VECTOR  = 0000000B
IDB$K-LENGTH  = 00000038
IDB$-ADP      = 00000014
IDB$-CSR      = 00000000
IDB$-OWNER    = 00000004
IDB$W-UNITS   = 0000000C
IDB-COLUMN-1  = 0000162A R      03
IDB-COLUMN-2  = 0000165A R    03
IDB-COLUMN-3  = 0000168A R    03
IDB-VECTOR    = 000016AA R    03
IOS$-FCODE    = 00000006
IOSV-FCODE    = 00000000
IOS-ACCESS    = 00000032
IOS-ACPCONTROL = 00000038
IOS-AVAILABLE = 00000011
IOS-CREATE    = 00000033
IOS-DEACCESS  = 00000034
IOS-DELETE    = 00000035
IOS-DSE       = 00000015
IOS-ERASETAPE = 00000006
IOS-MODIFY    = 00000036
IOS-NOP       = 00000000
IOS-PACKACK   = 00000008
IOS-READLBLK  = 00000021
IOS-READPBLK  = 0000000C
IOS-READVBLK  = 00000031
IOS-RECAL     = 00000003
IOS-REWIND    = 00000024

```


Page 70
(20)

```

= 00000000
= 00000007
= 00000006
= 00000002
= 00000005
= 0000000F
= 00000001
= 00000004
***** X 03
***** X 03
00000060 R 02
00000915 R R 04
00000E21 R R 04
00000E33 R R 04
00001065 R 04
= 00000000
= 00000002
= 00000000
00002355 R 03
***** X 03
***** X 03
00000000 0 04

```

[illegible]

DEVICE
Symbol table

Display device data structures

L 16

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 71
(20)

```

PBSV_MAINT          = 00000000
PBSV_PORT_TYP       = 00000000
PBSV_STATE          = 00000001
PBSV_TIM            = 00000000
PBSW_RETRY          = 00000022
PBSW_STATE          = 00000012
PBSW_STS            = 00000044
PB_CABLES           = 00001BD6 R      03
PB_COLUMN_1         = 00001A38 R      03
PB_COLUMN_2         = 00001AB8 R      03
PB_DUALPATH         = 00001BBD R      03
PB_LCLSTATE         = 00001C51 R      03
PB_LOOP             = 00001854 R      03
PB_RMTSTATE         = 00001B38 R      03
PB_RPORT_TYP        = 00001B8A R      03
PB_RPORT_TYPE       = 00000058 R      03
PB_RSTATE           = 00000038 R      03
PB_STATE            = 00000010 R      03
PB_STATUS           = 00000000 R      03
PCBST_LNAME         = 00000070
PDVNM_B_NODES2      = 00000022
PDVNM_K_LENGTH      = 00000024
PDVNM_T_DDC         = 00000010
PDVNM_T_NODE        = 00000000
PDVNM_W_UNIT        = 00000020
PRINT               = ***** X      03
PRINT_CDRP          = 00002823 R      03
PRINT_COLUMNS       = ***** X      03
PRINT_COLUMN_VALUE  = ***** X      03
PRINT_IRP           = 000029D0 R      03
PROCESS_2P_DDB      = 00001D7C R      03
QUEUE_NOTEMPTY      = 00000577 R      02
QUEUE_TITLE         = 00002962 R      03
RABSL_RBF           = ***** X      03
RABSW_RSZ           = ***** X      03
REALTIME_TYPE       = 000006D0 R      03
REQUEST_STATUS      = 00000A10 R      03
RETRY_CNT           = 00003419 R      03
RSTRY_CDRP          = 00003405 R      03
SB                  = 00000000 R      02
SB$B_ENBMSK         = 0000005A
SB$B_HWVERS         = 00000038
SB$B_SYSTEMID       = 00000018
SB$B_TYPE           = 0000000A
SB$C_LENGTH         = 00000060
SB$K_LENGTH         = 00000060
SB$L_DDB            = 00000054
SB$L_FLINK          = 00000000
SB$L_PBFL           = 0000000C
SB$Q_SWINCARN       = 0000002C
SB$Q_SWINCARN2      = 00000030
SB$S_NODENAME       = 00000010
SB$T_HWTYPE         = 00000034
SB$T_NODENAME       = 00000044
SB$T_SWTYPE         = 00000024
SB$T_SWVERS         = 00000028
SBSW_MAXDG          = 00000020

```

```

SBSW_MAXMSG         = 00000022
SBSW_TIMEOUT        = 00000058
SB_6BYTES           = 000019F4 R      03
SB_COLUMN_1         = 00001914 R      03
SB_COLUMN_2         = 00001984 R      03
SB_FAO_6BYTES       = 00000DEE R      04
SB_FAO_ASCIC        = 00000E00 R      04
SB_LWCHAR           = 00001A14 R      03
SCH$GL_PCBVEC       = ***** X      03
SCOM_TYPE           = 00000480 R      03
SC$SGA_LOCALSB      = ***** X      03
SC$SGQ_CONFIG       = ***** X      03
SECOND              = 000031A7 R      03
SETUP_PRIMARY        = 00001DC4 R      03
SET_HEADING         = ***** X      03
SHOW_ACPQ           = 000025B3 R      03
SHOW_CDDB           = 0000313C R      03
SHOW_CONTROLLER      = 00000FE1 R      03
SHOW_DDBS           = 00000DFD R      03
SHOW_IOQ            = 000024C9 R      03
SHOW_SYSTEM_BLOCK   = 000017D8 RG     03
SHOW_UCB            = 00001C7B R      03
SHOW_VCB            = 00002AB1 R      03
SIZ...              = 00000001
SKIP_LINES          = ***** X      03
SKIP_SB             = 0000103A R      03
SKIP_SECOND_CRB     = 000011E8 R      03
SS$ROSUCHDEV        = ***** X      03
SYS$FAO             = ***** X      03
SYS$FAOL            = ***** GX     03
SYS$PUT             = ***** GX     03
TAPE_TYPE           = 00000428 R      03
TERM_TYPE           = 00000558 R      03
THIS_PRIMARY        = 0000109B R      04
THIS_SECONDARY      = 000010DD R      04
TPASL_NUMBER        = 0000001C
TPASL_TOKENCNT      = 00000010
TRANSLATE_ADDRESS   = ***** X      03
TRANSLATE_BITS      = ***** X      03
TRYMEM              = ***** X      03
UCB                 = 000000F9 R      02
UCB$B_DEVCLASS      = 00000040
UCB$B_DEVTYPE       = 00000041
UCB$B_DIPL          = 0000005E
UCB$B_ERTCNT        = 00000080
UCB$B_ERTMAX        = 00000081
UCB$B_FIPL          = 0000000B
UCB$B_ONLCNT        = 000000AE
UCB$B_TYPE          = 0000000A
UCB$K_LCL_DISK_LENGTH = 000000CC
UCB$L_2P_CDDB       = 000000C0
UCB$L_AMB           = 00000060
UCB$L_CDDB          = 0000008C
UCB$L_CPID          = 00000020
UCB$L_CRB           = 00000024
UCB$L_DDB           = 00000028
UCB$L_DDT           = 00000088

```

DEVICE
Symbol table

Display device data structures

M 16

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 72
(20)

```
UCBSL_DEVCHAR      = 00000038
UCBSL_DEVCHAR2     = 0000003C
UCBSL_DEVDEPEND    = 00000044
UCBSL_DEVDEPN2     = 00000048
UCBSL_DP_ALTUCB    = 000000A8
UCBSL_DP_DDB       = 000000A0
UCBSL_DP_LINK      = 000000A4
UCBSL_DUETIM       = 0000006C
UCBSL_FPC          = 0000000C
UCBSL_FR3          = 00000010
UCBSL_FR4          = 00000014
UCBSL_IOQFL        = 0000004C
UCBSL_IRP          = 00000058
UCBSL_JNL_MCSID    = 00000084
UCBSL_LINR         = 00000030
UCBSL_LOCKID       = 00000020
UCBSL_LOGADR       = 00000074
UCBSL_OPCNT        = 00000070
UCBSL_ORB          = 0000001C
UCBSL_PDT          = 00000084
UCBSL_PID          = 0000002C
UCBSL_STS          = 00000064
UCBSL_SVAPTE       = 00000078
UCBSL_SVPN         = 00000074
UCBSL_TL_PHYUCB    = 000000A0
UCBSL_VCB          = 00000034
UCBSV_BSY          = 00000008
UCBSV_CANCEL       = 00000003
UCBSV_DEADMO       = 0000000A
UCBSV_DELETEUCB    = 00000010
UCBSV_ERLOGIP      = 00000002
UCBSV_INT          = 00000001
UCBSV_INTTYPE      = 00000007
UCBSV_LCL_VALID    = 00000011
UCBSV_MNTVERIP     = 0000000E
UCBSV_MNTVERPND    = 00000013
UCBSV_MOUNTING     = 00000009
UCBSV_ONLINE       = 00000004
UCBSV_POWER        = 00000005
UCBSV_SUPMMSG      = 00000012
UCBSV_TEMPLATE     = 0000000D
UCBSV_TM           = 00000000
UCBSV_TIMEOUT      = 00000006
UCBSV_UNLOAD       = 0000000C
UCBSV_VALID        = 0000000B
UCBSV_WRONGVOL     = 0000000F
UCBSW_BCNT         = 0000007E
UCBSW_BOFF         = 0000007C
UCBSW_DEVBUFSIZ    = 00000042
UCBSW_DEVSTS       = 00000068
UCBSW_ERRCNT       = 00000082
UCBSW_REFC         = 0000005C
UCBSW_RWAITCNT     = 00000056
UCBSW_SIZE         = 00000008
UCBSW_STS          = 00000064
UCBSW_UNIT         = 00000054
UCB_2PCDDDB        = 000023E2 R
```

03

```
UCB_2PCDDDB        = 000024A4 R 03
UCB_ACT_NOP        = 000022D5 R 03
UCB_ACT_NOP_A      = 000023BD R 03
UCB_ACT_NOP_B      = 000024C6 R 03
UCB_ACT_UB         = 0000227A R 03
UCB_ACT_XL         = 00002330 R 03
UCB_ACT_XL_NEQ     = 000022B1 R 03
UCB_ACT_XW         = 00002467 R 03
UCB_ALLOCLASS      = 00002271 R 03
UCB_ALTUCB         = 00002283 R 03
UCB_BSY            = 000022A9 R 03
UCB_CDDDB          = 000023C0 R 03
UCB_CLSTYP         = 000022BB R 03
UCB_COLUMN_1       = 00001FC1 R 03
UCB_COLUMN_2       = 00002071 R 03
UCB_COLUMN_3       = 00002151 R 03
UCB_CPID           = 000022C5 R 03
UCB_DDB            = 0000057C R 02
UCB_DUETIM         = 000022D8 R 03
UCB_IPLS           = 000022E3 R 03
UCB_LNM            = 00002301 R 03
UCB_LOCKID         = 00002327 R 03
UCB_MCSID          = 00002339 R 03
UCB_ONLCNT         = 00002347 R 03
UCB_PDT            = 00002388 R 03
UCB_RETRY          = 00002408 R 03
UCB_RETRY_FAO      = 0000118C R 04
UCB_RET_2XBYTES    = 000022EB R 03
UCB_RWAITCNT       = 00002449 R 03
UCB_SIZE           = 000000CC
UCB_SVPN           = 00002470 R 03
UCB_TEST_RETRY_FAO = 0000119C R 04
UCB_TWO_BYTES      = 0000117B R 04
UCB_UIC_CSTR1      = 00001168 R 04
UCB_VCB            = 0000247E R 03
UNIT_STATUS        = 000000B8 R 03
UNKNOWN            = 00001160 R 04
VCB                = 00000331 R 02
VCBSB_CUR_RVN      = 0000002F
VCBSB_JNL_MODE     = 00000044
VCBSB_RESFILES     = 0000004F
VCBSB_STATUS       = 0000000B
VCBSB_STATUS2      = 00000053
VCBSB_TM           = 0000002E
VCBSB_TYPE         = 0000000A
VCBSB_WINDOW       = 00000048
VCBSB_LENGTH       = 000000EC
VCBSL_AQB          = 00000010
VCBSL_BLOCKFL      = 00000000
VCBSL_BLOCKID      = 0000008C
VCBSL_CACHE        = 00000058
VCBSL_FCBL         = 00000000
VCBSL_FREE         = 00000040
VCBSL_JNL_CHAR     = 00000024
VCBSL_JNL_JFTA     = 00000028
VCBSL_JNL_JMT      = 00000034
VCBSL_JNL_MASK     = 00000048
```

DEVICE
Symbol table

Display device data structures

B 1

16-SEP-1984 01:26:37 VAX/VMS Macro V04-00
5-SEP-1984 03:32:17 [SDA.SRC]DEVICE.MAR;1

Page 73
(20)

DUM
V04

VCBSL_MAXFILES	= 00000044		
VCBSL_MVL	= 00000034		
VCBSL_QUOCACHE	= 0000005C		
VCBSL_QUOTAFCB	= 00000054		
VCBSL_RVT	= 00000020		
VCBSL_ST_RECORD	= 00000030		
VCBSL_VOLCKID	= 0000007C		
VCBSL_VPFL	= 0000003C		
VCBST_VOLCKNAM	= 00000080		
VCBST_VOLNAME	= 00000014		
VCBSV_BLANK	= 0000000A		
VCBSV_CANCELIO	= 00000005		
VCBSV_EBCDIC	= 00000005		
VCBSV_ENUSEREOT	= 00000009		
VCBSV_ERASE	= 00000003		
VCBSV_EXTFID	= 00000005		
VCBSV_GROUP	= 00000006		
VCBSV_HOMBLKBD	= 00000002		
VCBSV_IDXHDBAD	= 00000003		
VCBSV_INIT	= 00000008		
VCBSV_INTCHG	= 00000004		
VCBSV_JNL_DISK	= 00000000		
VCBSV_JNL_TAPE	= 00000001		
VCBSV_JNL_TMPFI	= 00000002		
VCBSV_LOGICEOVS	= 00000001		
VCBSV_MOUNTVER	= 00000002		
VCBSV_MUSTCLOSE	= 00000006		
VCBSV_NOALLOC	= 00000004		
VCBSV_NOAUTO	= 0000000C		
VCBSV_NOCACHE	= 00000001		
VCBSV_NOHIGHWATER	= 00000004		
VCBSV_NOVOL2	= 00000006		
VCBSV_NOWRITE	= 00000007		
VCBSV_OVRACC	= 00000001		
VCBSV_OVREXP	= 00000000		
VCBSV_OVRLBL	= 00000002		
VCBSV_OVRSETID	= 00000003		
VCBSV_OVRVOLO	= 0000000D		
VCBSV_PARTFILE	= 00000000		
VCBSV_STARFILE	= 00000008		
VCBSV_SYSTEM	= 00000007		
VCBSV_WAIMOUVOL	= 00000002		
VCBSV_WAIREWIND	= 00000003		
VCBSV_WAIUSRLBL	= 00000004		
VCBSV_WRITE_THRU	= 00000000		
VCBSV_WRITE_IF	= 00000000		
VCBSV_WRITE_SM	= 00000001		
VCBSW_CLUSTER	= 0000003C		
VCBSW_EXTEND	= 0000003E		
VCBSW_JNL_COP	= 00000045		
VCBSW_MCOONT	= 0000004C		
VCBSW_MODE	= 0000002C		
VCBSW_RECORDSZ	= 00000050		
VCBSW_RVN	= 0000000E		
VCBSW_TRANS	= 0000000C		
VCB_DISK	00002C8B	R	03
VCB_DISK_COL_1	00002E4C	R	03

VCB_DISK_COL_2	00002EBC	R	03
VCB_DISK_COL_3	00002F2C	R	03
VCB_DISK_STATUS	000037D8	R	03
VCB_DISK_STATUS2	00000820	R	03
VCB_FOREIGN	00002D1D	R	03
VCB_JNL_COL_1	000030AC	R	03
VCB_JNL_COL_2	000030DC	R	03
VCB_JNL_COL_3	0000310C	R	03
VCB_JOURNAL	00002DE9	R	03
VCB_JOURNAL_CHAR	00000908	R	03
VCB_NET	00002DC8	R	03
VCB_NET_COL_1	0000304C	R	03
VCB_NET_COL_2	0000306C	R	03
VCB_NET_COL_3	0000308C	R	03
VCB_SHOW_ACPQ	00002E46	R	03
VCB_TAPE	00002D1D	R	03
VCB_TAPE_COL_1	00002F9C	R	03
VCB_TAPE_COL_2	00002FDC	R	03
VCB_TAPE_COL_3	0000300C	R	03
VCB_TAPE_MODE	00000898	R	03
VCB_TAPE_STATUS	00000850	R	03
VECSB_DATAPATH	= 00000013		
VECSB_NUMREG	= 00000012		
VECSL_ADP	= 00000014		
VECSL_IDB	= 00000008		
VECSL_INITIAL	= 0000000C		
VECSL_INTSER	= 00000004		
VECSL_START	= 0000001C		
VECSL_UNITDISC	= 00000020		
VECSL_UNITINIT	= 00000018		
VECSQ_DISPATCH	= 00000000		
VECSS_DATAPATH	= 00000005		
VECSS_MAPREG	= 0000000F		
VECSV_DATAPATH	= 00000000		
VECSV_LWAE	= 00000005		
VECSV_MAPLOCK	= 0000000F		
VECSV_MAPREG	= 00000000		
VECSV_PATHLOCK	= 00000007		
VECSW_MAPREG	= 00000010		
VEC_COLUMN_1	0000149E	R	03
VEC_COLUMN_2	000014DE	R	03
VEC_COLUMN_3	0000151E	R	03
VEC_DATAPATH	0000155E	R	03
VEC_FAO_DATAPATH	00000B47	R	04
VEC_FAO_MAPREG	00000B58	R	04
VEC_LOCKED	00000B71	R	04
VEC_LWAE	00000B6B	R	04
VEC_MAPREG	000015DC	R	03
VEC_TEST_UBA	000015BE	R	03
VIRTUAL_TERMINAL	0000111F	R	04
WORKSTATION_TYPE	000006B0	R	03

+-----+
! Psect synopsis !
+-----+

PSECT name	Allocation	PSECT No.	Attributes
ABS	00000000 (0.)	00 (0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
\$ABSS	00000024 (36.)	01 (1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
SDADATA	00000580 (1408.)	02 (2.)	NOPIC USR CON REL LCL NOSHR NOEXE RD WRT NOVEC BYTE
DEVICE	0000342A (13354.)	03 (3.)	NOPIC USR CON REL LCL NOSHR EXE RD NOWRT NOVEC LONG
LITERALS	00001B70 (7024.)	04 (4.)	NOPIC USR CON REL LCL NOSHR EXE RD NOWRT NOVEC BYTE

+-----+
Performance indicators !
+-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	29	00:00:00.04	00:00:00.99
Command processing	108	00:00:00.41	00:00:03.28
Pass 1	1290	00:00:43.46	00:02:42.73
Symbol table sort	0	00:00:03.73	00:00:14.02
Pass 2	919	00:00:10.33	00:00:34.74
Symbol table output	1	00:00:00.44	00:00:01.57
Psect synopsis output	0	00:00:00.02	00:00:00.01
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	2349	00:00:58.45	00:03:37.38

The working set limit was 3000 pages.
381141 bytes (745 pages) of virtual memory were used to buffer the intermediate code.
There were 190 pages of symbol table space allocated to hold 3185 non-local and 393 local symbols.
2914 source lines were read in Pass 1, producing 108 object records in Pass 2.
69 pages of virtual memory were used to define 64 macros.

+-----+
! Macro library statistics !
+-----+

Macro library name	Macros defined
_\$255\$DUA28:[SDA.OBJ]SDALIB.MLB;1	20
_\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	21
_\$255\$DUA28:[SYSLIB]STARLET.MLB;2	14
TOTALS (all libraries)	55

3409 GETS were required to define 55 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:DEVICE/OBJ=OBJ\$:DEVICE MSRC\$:DEVICE/UPDATE=(ENH\$:DEVICE)+EXECMLS/LIB+LIB\$:SDALIB/LIB

0351 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY

1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24	25	26	27	28	29	30	31	32	33	34	35	36	37	38	39	40	41	42	43	44	45	46	47	48	49	50	51	52	53	54	55	56	57	58	59	60	61	62	63	64	65	66	67	68	69	70	71	72	73	74	75	76	77	78	79	80	81	82	83	84	85	86	87	88	89	90	91	92	93	94	95	96	97	98	99	100
101	102	103	104	105	106	107	108	109	110	111	112	113	114	115	116	117	118	119	120	121	122	123	124	125	126	127	128	129	130	131	132	133	134	135	136	137	138	139	140	141	142	143	144	145	146	147	148	149	150	151	152	153	154	155	156	157	158	159	160	161	162	163	164	165	166	167	168	169	170	171	172	173	174	175	176	177	178	179	180	181	182	183	184	185	186	187	188	189	190	191	192	193	194	195	196	197	198	199	200
201	202	203	204	205	206	207	208	209	210	211	212	213	214	215	216	217	218	219	220	221	222	223	224	225	226	227	228	229	230	231	232	233	234	235	236	237	238	239	240	241	242	243	244	245	246	247	248	249	250	251	252	253	254	255	256	257	258	259	260	261	262	263	264	265	266	267	268	269	270	271	272	273	274	275	276	277	278	279	280	281	282	283	284	285	286	287	288	289	290	291	292	293	294	295	296	297	298	299	300
301	302	303	304	305	306	307	308	309	310	311	312	313	314	315	316	317	318	319	320	321	322	323	324	325	326	327	328	329	330	331	332	333	334	335	336	337	338	339	340	341	342	343	344	345	346	347	348	349	350	351	352	353	354	355	356	357	358	359	360	361	362	363	364	365	366	367	368	369	370	371	372	373	374	375	376	377	378	379	380	381	382	383	384	385	386	387	388	389	390	391	392	393	394	395	396	397	398	399	400
401	402	403	404	405	406	407	408	409	410	411	412	413	414	415	416	417	418	419	420	421	422	423	424	425	426	427	428	429	430	431	432	433	434	435	436	437	438	439	440	441	442	443	444	445	446	447	448	449	450	451	452	453	454	455	456	457	458	459	460	461	462	463	464	465	466	467	468	469	470	471	472	473	474	475	476	477	478	479	480	481	482	483	484	485	486	487	488	489	490	491	492	493	494	495	496	497	498	499	500
501	502	503	504	505	506	507	508	509	510	511	512	513	514	515	516	517	518	519	520	521	522	523	524	525	526	527	528	529	530	531	532	533	534	535	536	537	538	539	540	541	542	543	544	545	546	547	548	549	550	551	552	553	554	555	556	557	558	559	560	561	562	563	564	565	566	567	568	569	570	571	572	573	574	575	576	577	578	579	580	581	582	583	584	585	586	587	588	589	590	591	592	593	594	595	596	597	598	599	600
601	602	603	604	605	606	607	608	609	610	611	612	613	614	615	616	617	618	619	620	621	622	623	624	625	626	627	628	629	630	631	632	633	634	635	636	637	638	639	640	641	642	643	644	645	646	647	648	649	650	651	652	653	654	655	656	657	658	659	660	661	662	663	664	665	666	667	668	669	670	671	672	673	674	675	676	677	678	679	680	681	682	683	684	685	686	687	688	689	690	691	692	693	694	695	696	697	698	699	700
701	702	703	704	705	706	707	708	709	710	711	712	713	714	715	716	717	718	719	720	721	722	723	724	725	726	727	728	729	730	731	732	733	734	735	736	737	738	739	740	741	742	743	744	745	746	747	748	749	750	751	752	753	754	755	756	757	758	759	760	761	762	763	764	765	766	767	768	769	770	771	772	773	774	775	776	777	778	779	780	781	782	783	784	785	786	787	788	789	790	791	792	793	794	795	796	797	798	799	800
801	802	803	804	805	806	807	808	809	810	811	812	813	814	815	816	817	818	819	820	821	822	823	824	825	826	827	828	829	830	831	832	833	834	835	836	837	838	839	840	841	842	843	844	845	846	847	848	849	850	851	852	853	854	855	856	857	858	859	860	861	862	863	864	865	866	867	868	869	870	871	872	873	874	875	876	877	878	879	880	881	882	883	884	885	886	887	888	889	890	891	892	893	894	895	896	897	898	899	900
901	902	903	904	905	906	907	908	909	910	911	912	913	914	915	916	917	918	919	920	921	922	923	924	925	926	927	928	929	930	931	932	933	934	935	936	937	938	939	940	941	942	943	944	945	946	947	948	949	950	951	952	953	954	955	956	957	958	959	960	961	962	963	964	965	966	967	968	969	970	971	972	973	974	975	976	977	978	979	980	981	982	983	984	985	986	987	988	989	990	991	992	993	994	995	996	997	998	999	1000

0352

**DIGITAL
CONFIDE**